

MartexPO MT5 – Forex Expert Advisor

Version 1. August 2022

MartexPO MT5 («martingale», «Forex», Pending Orders) is a moderately aggressive advisor working on a martingale strategy and with the ability to hedge unprofitable positions. It differs from the [MartexMT5](#) EA in that it uses pending orders to open the first order and for hedging orders.

MartexPO MT5 EA can averaged not only their orders, but other orders opened by another EA or opened by the trader manually. To do this, simply set in EA the magic number -1 (minus one). The EA **MartexPO MT5** will be interesting for both beginners and experienced traders.

Features MartexPO MT5 EA

- works without indicators;
- to determine the direction of the first order, you can use Auto Trend;
- uses pending orders to open the first order and for hedging orders;
- automatic magic number, individual for each currency pair;
- martingale can be disabled, then the adviser will work with only one order;
- can average other, "not their" orders including those opened by the trader manually;
- common, single stop loss for several orders;
- virtual take profit, which can be moved manually;
- dynamic step between martingale orders;
- reducing the martingale multiplier to 1, with an increase in risk;
- breakeven for single orders and common for orders of one direction;
- trailing stop for single orders and common for orders of one direction;
- control over the use of Free margin, in case of excess - stop trading;
- closing orders by drawdown percentage;
- closing orders under a fixed profit plan;
- closing all positions on Equity;
- partial and full locking of loss positions (lock);
- automatic exit from the "lock" with the closing of all positions;
- limit on the number of open orders by martingale;
- restriction on the total lot size of all open orders of one direction;
- trade by time;
- sending messages to email about lack of funds and when trading stops;
- sending Push notifications to your smartphone about lack of funds and when trading stops;
- position management using "hot" buttons;
- works on both dollar (USD) and ruble accounts (RUR);
- works on accounts with quotes of 4 and 5 decimal places.

Importantly:

- Before starting the **MartexPO MT5** EA on a real account, first optimize it in the strategy tester on historical data (at least 3 months) of your broker.
- For preliminary optimization, you can select the "Open prices only..." mode to check and optimize more accurately, use the "Every tick..." mode.
- How to optimize the EA see here <https://www.mql5.com/en/articles/1385>

Hot buttons

Hot buttons are designed for quick execution of one command.



Close All – closes absolutely all open orders on the current currency pair and removes all pending orders regardless of the magic number.

Close Loss – closes only orders with loss on the current currency pair.

Close Profit – closes only orders with profit on the current currency pair.

Delete PO – delete pending orders on the current currency pair.

Delete SL – deleting of take profit and stop loss for all orders on the current currency pair.

Block 1. GENERAL SETTINGS

Variable	Value
___ 1. GENERAL SETTINGS ___	
↗ Trading	true
01 Magic number (0 - automat)	0
☰ Positions: >	Long & Short
☰ Working timeframe: >	5 Minutes
½ Initial lot in the series	0.01
01 Take Profit	20
↗ Update the take profit level	true
↗ Virtual take profit	false
01 Stop Loss	0
↗ Total stop loss	false
☰ Breakeven, mode: >	Disabled
01 Profit to enable a breakeven	14
01 Breakeven level	2
01 Slippage	3

Buttons: Load, Save, OK, Отмена, Reset

Trading = true, if you select false, then the EA will no longer open new orders, but all other functions of the EA will continue to work (trailing stop, breakeven, closing with a fixed profit, etc.).

Magic Number (0-automat) = 0 - allows you to specify to the EA which orders (with which magic number) it should track. If the magic number = 0, the EA will automatically select the original magic number (5-digit), which will differ depending on the currency pair on which it is installed. Instead of zero, you can set your magic number. If you put "-1" instead of 0, the EA will take into account and monitor all orders that are currently available on the chart, including orders opened manually.

Importantly: if the magic number is "-1", then the EA will not open new orders, but all other functions of the adviser (martingale, trailing stop, breakeven, hot buttons, etc.) will continue their work as usual.

Positions:

- **Long only** - open and trawl only buy orders;
- **Short only** - open and trail only sell orders;
- **Long & Short** - for orders of all directions.

01 Magic number (0 - automat)	0
Positions: >	Long & Short
Working timeframe: >	Long only Short only
1/2 Initial lot in the series	Long & Short
01 Take Profit	20

Working timeframe: = «5 Minutes» - selecting the timeframe for opening the first order. Use the mouse to select the desired timeframe from the drop-down menu. If you select "current", the indicators will automatically be adjusted for the period of the chart, which is currently set in the open terminal window.

Positions: >	Long & Short
Working timeframe: >	5 Minutes
1/2 Initial lot in the series	current 1 Minute
01 Take Profit	2 Minutes
Update the take profit level	3 Minutes
Virtual take profit	4 Minutes
01 Stop Loss	5 Minutes
Total stop loss	6 Minutes
Breakeven, mode: >	10 Minutes
01 Profit to enable a breakeven	12 Minutes
01 Breakeven level	15 Minutes
01 Slippage	20 Minutes
	30 Minutes
	1 Hour
	2 Hours
	3 Hours
	4 Hours
	...

Load
Save

Importantly: the EA does not open orders on the working timeframe, however, the choice of working timeframe may affect the work of other functions of the adviser, opening martingale orders, placing and moving hedging orders. The smaller the working timeframe, the faster the listed functions work, but the more false signals can be.

Initial lot in the series = 0.01 - the size of the first lot.

Take Profit = 20.

Update the take profit level = true - when manually opening a new order or closing one of the orders in the series, the EA will automatically calculate and set a new level of averaged take profit.

Virtual take profit = false - invisible to the broker take profit, it can be moved with your hands on the chart, orders are closed when the price reaches the take profit line, while the total profit for all orders must be greater than 0 otherwise orders will not be closed.

Stop Loss = 0.

Total stop loss = false – if true, the stop loss for all orders will be at the same level, set for the first order.

Breakeven, mode:

- **Usual** – breakeven for each order, individually;
- **General, united** – the average breakeven from the sum of profitable and unprofitable orders of the same direction;
- **Disabled** – breakeven is disabled and does not work.

Update the take profit level	false
Breakeven, mode: >	Disabled
01 Profit to enable a breakeven	Usual
01 Breakeven level	General, united
01 Slippage	Disabled
	3

Profit to enable a breakeven = 14 – level of take-profit in points, at which a breakeven is enabled.

Breakeven level = 2 – sets the level, at which a stop-loss must be moved: if set to 1, then the position will be closed, when the profit is 1 point; if set to 0, then the position will be closed with the profit of 0 points.

Slippage = 3 - the level of slippage in points on the volatile market it is better to increase.

Block 2. MARTINGALE PARAMETERS

The screenshot shows a software window with two tabs: 'Common' and 'Inputs'. The 'Inputs' tab is active, displaying a table of parameters for the Martingale strategy. The table has two columns: 'Variable' and 'Value'. The parameters are as follows:

Variable	Value
2. MARTINGALE PARAMETERS	
↗ Martingale	true
½ Fixed martingale lot	0.0
½ Multiplier	1.5
01 Max orders with a set multiplier	8
01 Step between martingale orders	3
01 Indent for pending orders	6
↗ Moving pending orders	true
↗ Dynamic step	true
½ Multiplier for dynamic step	1.5
01 Max number of open orders	16
½ Maximum amount of lots	10.0

Below the table, there are three buttons: 'Load', 'Save', and 'OK'. At the bottom right, there are two more buttons: 'Отмена' (Cancel) and 'Reset'.

Martingale = true, if false, the EA will not open averaging orders.

Fixed martingale lot = 0.0 – a fixed lot for all subsequent martingale orders, regardless of the value of the martingale multiplier. If = 0.0 – does not work!

Multiplier = 1.5 - martingale coefficient, the increase in the lot volume of the subsequent order by a given coefficient. If the multiplier = 1.0, then the EA will place orders only with a lot equal to the lot volume of the previous order.

Max orders with a set multiplier = 8 – the number of open orders opened in the same direction as the first order and with a set martingale multiplier. When opening new orders above the set value, the martingale multiplier is automatically reduced to 1.0. And the size of the total take profit is halved! For example: if the initial lot is 0.01, the take profit is 12, the multiplier is 1.6 and the limit is 6 orders, then the sixth order will have a volume of 0.13 and all subsequent new orders (7,8,9, etc.) will have the same volume of 0.13! The martingale multiplier will decrease to 1.0 after opening the sixth order. And the total take profit will decrease to 6. These settings will allow the adviser to wait out a protracted price correction and close all positions faster.

Step between martingale orders = 3 - step (distance) in points between martingale orders.

Indent for pending = 6 – indent of a pending order from the price (Bid or Ask).

Moving pending orders = true – allow movement of pending orders.

Dynamic step = false - allow to increase the step between orders after opening a new order.

Multiplier for dynamic step = 1.5 - increasing the step between orders by a given coefficient.

Max number of open orders = 16 - limiting the number of all open orders in one direction.

Maximum amount of lots = 10.0 - limit on the total volume of all lots, open orders, one direction.

Block 3. RISK MANAGEMENT

3. RISK MANAGEMENT	
1/2 Minimum free margin in %	30.0
1/2 Close all orders at drawdown in %	100.0
↗ Fixed profit	false
1/2 Profit in the deposit currency	10.0
↗ Close by Equity	false
01 Amount of Equity, in the currency of t...	3500

Minimum free margin in % = 30 – the minimum level of free margin in percent, if there are no open positions, then the level of free margin is 100%.

Importantly!

- When the level drops to the set value (for example: 30), trading will be stopped and the EA will not open new orders.
- If hedging is enabled, then with the minimum value of free margin, the EA will enter a full “lock”, open an order in the opposite direction with such a volume that the volumes of opposite positions become equal.

Close all orders at drawdown in % = 100 – if the drawdown reaches the set value, all orders will be closed and the EA will stop working. If you do not want to limit the work of the EA with this condition, set the value 100 here.

Fixed profit = false – if true, then when the fixed profit value is reached on the current pair (on which the EA is installed), the EA will close all orders.

Importantly: further work of the EA will be blocked until the beginning of the next day!

Profit in the deposit currency = 10.0 – the amount of fixed profit in the deposit currency. The profit is taken into account only for the current instrument (currency pair), and not all the profit in the terminal!

Close by Equity = false – if true, then close all open positions and delete all pending orders on the current currency pair when the account Equity reach the set value.

Amount of Equity, in the currency of the deposit = 3500 – the amount of Equity at which all orders will be closed, the value may be higher or lower than the account balance.

Importantly! If the orders were closed by Equity or if the drawdown exceeds the set percentage, then the further work of the EA will be blocked! To remove the lock, you need to reinstall the EA, i.e. remove it from the chart and install it again!

Block 4. HEDGING

The EA will start hedging if there is one of the conditions if:

- there is enough free margin, and the loss on the current currency pair is greater than or equal to the established limit;
- the free margin is less than (or equal to) the established minimum;
- the margin level will be below 110%.

In the last two cases, the EA will automatically fully lock unprofitable positions, regardless of whether the "Full "lock", immediately" command is enabled or not. With full varnishing, automatic exit from the lock is possible, but unlikely.

Importantly! When locking, breakeven will automatically work, but only for a hedging position. You can disable it by allowing the usual breakeven with its own parameters in the EA settings.

<u>4. HEDGING</u>	
↗ Hedging	false
½ Lot for hedging	0.0
½ If loss, hedging	10.0
01 Indent for a hedge order	10
↗ Moving hedge order	true
01 Distance for to move a hedge order	15
↗ Full "lock", immediately	false
½ Mini profit to exit the "lock"	1.0

Hedging = false, if true – enable hedging.

Lot for hedging = 0.0 – lot size for hedging.

Importantly: if 0.0, then the lot size is equal to the lot size of the initial lot in the series.

If loss, hedging = 10.0 – the EA will start hedging only if the loss on this currency pair reaches the set value (in this case \$10.0), in the deposit currency.

Indent for a hedge order = 10 – indent of the hedging pending order from the price (Bid or Ask).

Moving hedge order = true – allow movement of the hedging pending order.

Distance for to move a hedge order = 15 – distance of a pending order from the price in points for move the order.

Full "lock", immediately = false – locking will be partial, which will allow the adviser to automatically exit the "lock", if = true, then locking will immediately be full.

Mini profit to exit the "lock" = 1.0 – the minimum profit to exit the "lock" in the deposit currency, you can set any other value not lower than 0!

Block 5. AUTO TREND

AutoTrend using indicators to determine the direction of the trend for the selected timeframe. AutoTrend will only be used to select the direction when opening the first order. It is not used to determine the direction of martingale orders!

5. AUTO TREND	
AT indicators: >	One MA
Timeframe for AT: >	1 Hour
01 Long MA period (for MA, and two MAs)	13
01 Long MA shift	0
Long MA method: >	Exponential
Long MA price: >	Close price
01 Short MA period (for two MAs)	8
01 Short MA shift	0
Short MA type: >	Exponential
Short MA price: >	Close price

AT indicators: – choice of indicators for AutoTrend

- **One MA** – one moving average.
- **Two MAs** – two moving averages.
- **Disabled** – do not use auto trend.

5. AUTO TREND	
AT indicators: >	One MA
Timeframe for AT: >	One MA
01 Long MA period (for MA, and two MAs)	Two MAs
01 Long MA shift	Disabled
	0

Timeframe for AT: = «30 Minutes» - select the timeframe of indicators AutoTrend. Use the mouse to select the desired timeframe from the drop-down menu. If you select "current", the indicators will automatically be adjusted for the period of the chart, which is currently set in the open terminal window.

AT indicators: >	One MA
Timeframe for AT: >	1 Hour
01 Long MA period (for MA, and two MAs)	current
01 Long MA shift	1 Minute
Long MA method: >	2 Minutes
Long MA price: >	3 Minutes
01 Short MA period (for two MAs)	4 Minutes
01 Short MA shift	5 Minutes
Short MA type: >	6 Minutes
Short MA price: >	10 Minutes
	12 Minutes
	15 Minutes
	20 Minutes
	30 Minutes

Long MA period (for MA, and two MAs) = 35 - period of the moving average, if "Two MAs" is selected, then this is the period of the long moving average.

Long MA shift = 0.

Long MA method: = Exponential.

01 Long MA shift	0
Long MA method: >	Exponential
Long MA price: >	Simple
01 Short MA period (for two MAs)	Exponential
01 Short MA shift	Smoothed
	Linear weighted

Long MA price: = Close price.

Long MA method: >	Exponential
Long MA price: >	Close price
01 Short MA period (for two MAs)	Close price
01 Short MA shift	Open price
Short MA type: >	High price
Short MA price: >	Low price
	Median price
	Typical price
6. TRAILING STOP	Weighted price

Short MA period (for two MAs) = 13 – the period for a short moving average only if “Two MAs” is selected, does not work for other options.

Short MA shift = 0.

Short MA method: = Exponential.

01 Short MA shift	0
Short MA type: >	Exponential
Short MA price: >	Simple
6. TRAILING STOP	Exponential
	Smoothed
Mode trailing stop: >	Linear weighted

Short MA price: = Close price.

Short MA type: >	Exponential
Short MA price: >	Close price
6. TRAILING STOP	Close price
	Open price
Mode trailing stop: >	High price
Timeframe for trailing stop: >	Low price
Trailing stop by: >	Median price
	Typical price
01 Trailing stop level	Weighted price

Block 6. TRAILING STOP

6. TRAILING STOP	
Mode trailing stop: >	Disabled
Timeframe for trailing stop: >	1 Hour
Trailing stop by: >	Points
01 Trailing stop level	20
01 Trailing step	2
01 Indent from High/Low	2

Mode trailing stop: – the choice of strategy is the trailing stop:

- **Normal** - standard trailing stop, starts trail only when there is profit;
- **Total** - by one (average) stop loss closes all open orders in one direction, including losing orders;
- **Disabled** - trailing stop is disabled.

6. TRAILING STOP	
Mode trailing stop: >	Disabled
Timeframe for trailing stop: >	Normal
Trailing stop by: >	Total
	Disabled
01 Trailing stop level	20

Timeframe for trailing stop: = «1 Hour» - choice of the timeframe by which you want to work with trailing stop (except for Points).

___ 6. TRAILING STOP ___	
Mode trailing stop: >	Disabled
Timeframe for trailing stop: >	1 Hour
Trailing stop by: >	current
01 Trailing stop level	1 Minute
01 Trailing step	2 Minutes
01 Indent from High/Low	3 Minutes
	4 Minutes
	5 Minutes
	6 Minutes
___ 7. TRADE BY TIME ___	
Work on Friday	10 Minutes
Enable time	12 Minutes
	15 Minutes
	20 Minutes

Trailing stop by: - selecting the type of trailing stop

- **Points** - standard trailing stop by points;
- **High/Low** - the High/Low of the previous bar.

Timeframe for trailing stop: >	1 Hour
Trailing stop by: >	Points
01 Trailing stop level	Points
01 Trailing step	High/Low

Trailing stop level = 20 - trailing stop level in points.

Step trailing stop = 2 - step of trailing, if the profit is 20 points, trailing will move a stop-loss to 2 points.

Indent from High/Low = 2 - the distance in points from the stop loss to the maximum or the minimum of the bar.

Block 7. TRADE BY TIME

___ 7. TRADE BY TIME ___	
Work on Friday	true
Enable time	false
Start of operation time	02:00
End of operation time	22:00

You can set a period of time, during which the EA operates. After the set time has passed, the adviser will stop trading and will not open new orders. At the start of the new period of time (usually it is the next day) the EA will start its operation again. "End of operation time" can be set without reference to the "Start of operation time".

Work on Friday = true, work on Friday, if false – then, on Friday, the EA will no longer open new orders, but all other functions of the EA will continue to work (trailing stop, breakeven, closing with fixed profit, etc.).

Enable time = false - enable trade by time.

Start of operation time = 02:00 – time, when the EA starts to operate, set in hours and minutes.

End of operation time = 22:00 – the time, when the EA stops its operation, set in hours and minutes.

There are several options of how to set the operation time of the EA.

1st option: usual method – the operation time is set in hours and minutes a colon (:) between hours and minutes is put.

Time: 02:00 - 22:00

2nd option: setting up a year, a month, a day, an hour and a minute of start and end of the operation. A point is put between a year and a month, and also between a month and a day, then a space without a points put, and afterwards a colon (:) between an hour and a minute is put.

Time: 2022.07.18 02:00 - 2022.07.22 20:00

3rd option: setting up a day of start and a day of end of the operation are set. A year, a month and a day of start and a day of end of the operation are set up in the EA's settings. A point is put between a year and a month, but not after a day. The EA will start operation at 00:00 and stop operation at 00:00 on the pre-set day.

Time: 2022.07.25 - 2022.07.29

Block 8. OTHER SETTINGS

__ 8. OTHER SETTINGS __	
Language: >	English
Background: >	Light
Send email	false
Send push notification	false
Show options panel	true
Font size in messages: >	Medium
Show hot buttons	true

Load

Language = English - switch the language on the info panel can be Russian or English.

__ 8. OTHER SETTINGS __	
Language: >	English
Background: >	English
Send email	Russian
	Raise

Background = Dark - selects the color background of the chart Dark or Light.

Language: >	English
Background: >	Light
Send email	Light
Send push notification	Dark
	Raise

Send email = false - allow sending messages to email.


How to set up sending messages to e-mail see the "Help" to MetaTrader, section "Client Terminal Settings" hereinafter "Email".

Send push notification = false - allow you to send Push notifications to the mt4 mobile terminal installed in your smartphone.

How to set up sending notifications see the "Help" to MetaTrader section "Client Terminal Settings" hereinafter "Notifications".

Show options panel = true - displays textual information about the financial status of the account and currently active commands on the chart, if false, it does not show messages.

Font size in messages:



Show hot buttons = true - yes, show, false - no, do not show, "hot buttons" in the strategy tester do not work!

Advice: "Experts" tab in Terminal window can help you understand, how the EA operates.

Advice: use a Strategy Tester built-in MetaTrader in "**Visual mode**" mode to develop skills and gain a better understanding of principles of the EA operation.

You can obtain objective results by using "Every tick" mode. If accuracy of the results is not so important, and you want approximate results only, you can select "On the control points" mode.

The Strategy Tester will help you in developing your own strategy.

Deposit for martingale

What is the minimum deposit required to work on martingale? It is difficult to clearly answer this question, the amount of the required deposit depends on many factors, they can be divided into two large groups.

1. Trading conditions of your broker:

- your trading account type (standard or cent);
- the contract size of the base currency (100 000 or 10 000);
- the cost of the point in the size of 0.01 lot (0.1\$ or 0.01\$);
- the leverage is at least 1:500, but there are 1:1000 and 1:2000;
- the Stop Out level, when a broker forcibly closes your positions, one broker may have this indicator at 10%, and another at 40%;
- fixed or floating spread, with a fixed spread, optimization and order opening will be more accurate.

2. Your settings and your attitude to risk

For example, let's take one of the parameters, of the allowed number of open orders. Let's say you put there a limit of no more than 7 orders.

Your **broker A** has contract size 100 000 base currency and the cost of the point with lot 0.01 = 0.10 \$. 7 allowed orders is $0.01 + 0.02 + 0.04 + 0.08 + 0.16 + 0.32 + 0.64$ and this is 1.27 of the lot!

If leverage of 1:500 on EURUSD for this lot size 1.27 a margin will amount 293.70. USD (05.11.2021)!

What is the minimum deposit required for such a situation? At least three times more 900-1000 \$.

If the number of allowed orders is greater, the deposit must be increased accordingly.

Let's see how it will be at another **broker B** (example InstaForex) whose contract size 10 000 of the base currency and the value of the point is 0.01 \$.

On EURUSD with a leverage of 1:500 and lot 1.27, the deposit will be 29.37 USD (05.11.2021)! That is, the minimum deposit from this broker and with these settings can be only 90-100 \$.