



EXPERT ADVISOR · METATRADER 5

USER MANUAL

Setup, Operation & Input Reference Guide

About this manual

This manual explains how to install, configure and operate **Duelist**, a dual-module Expert Advisor for MetaTrader 5. One EA instance can run the **EURUSD** and **AUDCAD** modules independently from a single EURUSD chart.

Every input entry uses the name displayed in MetaTrader, shows the factory default and explains its operational effect. The guide also covers account requirements, symbol handling, the dashboard, manual close controls, live news handling and Strategy Tester use.

Hedging account required

Duelist cannot start on a **Netting** or **Exchange** account. If either trading module is enabled, the EA checks the account mode during initialization. An unsupported account triggers a prominent **DUELIST CANNOT START** alert and initialization stops. Ask your broker for an **MT5 Hedging** account before using the EA. Turning **Hedge Mode** off does not add Netting-account compatibility.

Scope of this guide. Internal entry logic, strategy calibration and advanced expert parameters are intentionally not documented. They are part of Duelist's protected trading model. This guide focuses on the settings and controls available to the user.

Independent trade ownership. Duelist identifies its positions by module symbol and Magic Number. Manual trades and positions opened by other Expert Advisors are excluded while their Magic Number differs from the matching Duelist module. They can still affect account-wide balance, equity, margin and available trading capacity. Reusing a Duelist Magic Number on the same symbol can cause positions to be counted, managed or closed as Duelist positions.

Contents

1	Getting Started	Setup checklist	2	Duelist — General	2 settings
3	EURUSD — Identity and Execution	6 settings	4	EURUSD — Lot Sizing and Total Stop-Loss	7 settings
5	EURUSD — Profit Goal and Grid Management	4 settings	6	EURUSD — News and Trading Calendar	9 settings
7	AUDCAD — Identity and Execution	6 settings	8	AUDCAD — Lot Sizing and Total Stop-Loss	7 settings
9	AUDCAD — Trading Calendar	6 settings	10	News Filter	4 settings
11	Dashboard and Appearance	2 settings + controls	12	Live Trading and Strategy Tester	Operational notes
13	Troubleshooting, Risk and Support	Quick reference			

1

Getting Started

Install Duelist once, attach it to a EURUSD chart and let the EA route both modules. The chart timeframe does not replace the strategy's internal timeframes; M15 is the standard reference setup.

STEP 01

Install the EA

Install Duelist through MQL5 Market or place the supplied product in MetaTrader 5, then refresh the Navigator. No external news file is required for backtests.

STEP 02

Open EURUSD

Open your broker's EURUSD symbol, including its normal prefix or suffix. The recommended chart timeframe is M15.

STEP 03

Attach Duelist

Drag Duelist onto the EURUSD chart. In the Common tab, allow algorithmic trading, then review the Inputs before confirming.

STEP 04

Select the modules

Enable EURUSD, AUDCAD or both. A single Duelist instance is sufficient; do not attach the same instance again to AUDCAD.

STEP 05

Choose lot sizing

Set Auto Lot and its risk preset, or disable Auto Lot and enter a fixed initial lot, separately for each module.

STEP 06

Verify readiness

Turn on the MetaTrader Algo Trading button. The dashboard should show **CONNECTED**, **ALGO READY** and a running status for each enabled module.

The account-mode check is blocking, not advisory

On a non-Hedging account, Duelist displays the account mode, tells the user that an MT5 Hedging account is required and returns an initialization failure. Changing inputs cannot make Duelist operate safely in Netting mode.

Attach Duelist only to the broker's EURUSD symbol

The current build does not automatically change or validate the chart symbol. The EURUSD engine operates on the symbol of the chart to which Duelist is attached. Open the broker's real tradable EURUSD variant — for example EURUSD, EURUSD+ or EURUSD.a — before attaching the EA. Never attach it to an unrelated chart.

Broker symbol handling

Duelist runs from the broker's EURUSD chart. When AUDCAD is enabled, it first looks for the matching broker variant — for example, a EURUSD suffix is paired with the equivalent AUDCAD suffix — and then searches the available symbols for a compatible AUDCAD instrument. If no tradable AUDCAD symbol is available, the module reports an initialization error.

Other positions on the account. Positions in other currency pairs, including pairs containing EUR and/or USD, do not consume Duelist's EURUSD basket depth. Manual or other-EA EURUSD trades are also excluded when their Magic Number differs from the EURUSD module. Broker margin, account permissions and account-level risk still apply normally.

2

Duelist — General

Master switches for the two trading engines. Each module has its own symbol, Magic Number, direction filter, lot sizing and protection settings.

Enable EURUSD Module

Default: **On**

Starts the EURUSD strategy engine on the chart symbol. Turn it off when you want Duelist to run only AUDCAD.

Note — Disabling a module prevents its engine from initializing. Review open positions before changing this setting, because positions belonging to a disabled module will not receive normal strategy management from that instance.

Enable AUDCAD Module

Default: **On**

Starts the integrated AUDCAD strategy engine. Duelist locates the broker's compatible AUDCAD symbol automatically; no AUDCAD chart is required.

Note — Both modules can operate at the same time. Within each module, independent BUY and SELL baskets may coexist when that module's Hedge Mode is on.

Changing inputs with open positions. Reinitializing an EA can affect session-only dashboard data and module state. Avoid changing module switches, Magic Numbers or core sizing settings while Duelist positions are open unless you fully understand the effect.

There is no public Pause All New Orders or Management Only input. Do not switch off a module to pause entries while it has open positions: disabling it also stops that module's normal strategy management. Keep the module enabled until it is flat.

EURUSD — Identity and Execution

Identifies EURUSD orders and controls permitted directions, Hedge Mode and the optional entry spread filter.

Magic Number

Default: **898936962**

Unique identifier stamped on EURUSD orders. Duelist uses the combination of symbol and Magic Number to recognize and manage the EURUSD module's own positions.

Note — Keep it different from the AUDCAD Magic Number and from other EAs. If you change it, the new instance will not adopt positions opened with the previous number.

Order Comment

Default: **Duelist**

Text attached to EURUSD orders to make them easier to identify in the Trade and History tabs. It does not determine ownership; the Magic Number does.

Trading Direction

Default: **Both Directions**

Allows both BUY and SELL basket seeds, BUY seeds only, or SELL seeds only for the EURUSD module.

Note — This governs the opening of a new directional basket. Existing baskets remain subject to normal management, including possible grid additions.

Enable Spread Filter

Default: **Off**

When on, blocks new EURUSD basket seeds while the current spread exceeds the configured maximum. Existing baskets continue to be managed, and grid additions are not suspended by this input.

Maximum Spread (points)

Default: **40.0**

Maximum EURUSD spread accepted for a new basket seed when the spread filter is enabled.

Note — The unit is broker points, not pips. On many five-digit Forex symbols, 10 points equal approximately 1 pip.

Hedge Mode

Default: **On**

When on, EURUSD keeps its standard behavior and may open independent BUY and SELL baskets at the same time. When off, a new opposite basket cannot open until every position in the active directional basket has closed.

Note — The check covers EURUSD positions matching the module symbol and Magic Number, whether the active side contains one position or a grid. It does not force a close or suspend same-direction grid additions and basket management.

4

EURUSD — Lot Sizing and Total Stop-Loss

Choose automatic balance-based sizing or a fixed initial lot, then optionally apply a module-level floating-loss limit.

Enable Auto Lot

Default: **On**

When on, Duelist calculates the EURUSD starting lot from the account balance and the selected risk preset. When off, it uses Fixed Initial Lot.

Auto Lot Risk and Reference Balance

Default: **Medium**

Selects the reference balance used to scale the EURUSD initial volume. Higher presets use a smaller reference balance and therefore increase volume sooner.

Risk labels are relative. They are sizing profiles, not a promise of a maximum loss percentage. The value controls the initial/base lot; a managed basket can later contain additional positions and different volumes.

EURUSD preset	Reference shown in MetaTrader	Relative sizing
Very Low	2500 per 0.01 lot	Smallest
Low	1800 per 0.01 lot	Lower
Medium	1200 per 0.01 lot	Default
High	500 per 0.01 lot	Largest

How Auto Lot steps — EURUSD uses the numeric account balance in native account-currency units. The calculated volume is $\max(1, \text{floor}(\text{balance} / \text{reference})) \times \text{broker minimum lot}$, then normalized to broker limits. Below the first reference, the result is still one broker-minimum lot; different presets can therefore show the same lot over part of a balance range.

Fixed Initial Lot (when Auto Lot is disabled)

Default: **0.01**

Starting volume used for EURUSD when Auto Lot is off. The requested value is normalized to the broker's permitted minimum, maximum and volume step.

Total Stop-Loss

Enable Total Stop Loss

Default: **Off**

Enables a module-wide floating-loss limit for Duelist's EURUSD positions. When the selected threshold is reached, the EA attempts to close all EURUSD positions belonging to this module.

Stop-Loss Measurement Mode

Default: **Account Currency**

Chooses whether the EURUSD total stop is measured as a fixed amount in the account currency or as a percentage of the current account balance.

Currency Stop Loss (0 = off)

Default: **0.0**

Floating-loss threshold in the account deposit currency. It is used only when Total Stop Loss is enabled and the measurement mode is Account Currency.

Percentage Stop Loss (0 = off)

Default: **0.0**

Floating-loss threshold as a percentage of account balance. It is used only when Total Stop Loss is enabled and the measurement mode is Percentage of Balance.

Execution note — A total stop sends market-close requests. Fast markets, gaps, freeze levels, FIFO rules or rejected requests can cause the final realized loss to differ from the threshold.

Emergency margin protection remains active. Turning Total Stop Loss off disables only the user-configured threshold. The EURUSD module retains an internal stop-out guard and may close matching Duelist positions if account margin becomes unsafe.

EURUSD — Profit Goal and Grid Management

Controls the base EURUSD basket objective, the maximum depth policy and margin-aware lot reduction.

Initial Profit Target

Default: **0.3**

Base net profit objective for a EURUSD basket, expressed in the account currency and scaled from the basket's initial lot. At 0.01 initial lot, the base objective is 0.30 account-currency units.

Note — This is basket-level management, not a fixed Take Profit distance on every ticket. The internal target calculation also accounts for applicable trading costs such as commission and swap.

Grid Depth Mode

Default: **Adaptive 3-5 Positions (Recommended)**

In Adaptive mode, Duelist selects a validated EURUSD basket ceiling within the built-in 3-to-5-position range. Fixed User Limit applies the maximum entered below.

Maximum Grid Positions (Fixed Mode; initial entry included)

Default: **5**

Maximum number of EURUSD positions in one directional basket when Grid Depth Mode is Fixed User Limit. The initial position counts toward this limit.

Note — This value determines basket depth only in Fixed User Limit mode. It must nevertheless remain between 1 and 128 because initialization validates it in both modes.

Reduce Lot to Available Margin When Required

Default: **On**

Allows EURUSD entry volume to be reduced when the requested size does not fit the available margin. If no valid volume fits, the order is not opened.

Note — This can reduce an individual order below its planned size; it does not override broker minimum volume or the EA's safety checks.

EURUSD — News and Trading Calendar

Select which economic-news impact levels pause new EURUSD basket seeds and which broker-server weekdays may start new baskets. These controls do not suspend management of existing baskets, and grid additions may still be opened.

Weekday On does not mean 24-hour admission. EURUSD basket seeds use broker server time: 03:00–20:59 Monday through Thursday and 03:00–12:59 Friday. The weekday switches grant permission inside those sessions; they do not remove the built-in hour filter.

Pause for High Impact News

Default: **On**

Pauses new EURUSD basket seeds around qualifying high-impact events found by the active live or tester news source.

Pause for Medium Impact News

Default: **Off**

Adds qualifying medium-impact events to the EURUSD news blackout when enabled.

Pause for Low Impact News

Default: **Off**

Adds qualifying low-impact events to the EURUSD news blackout when enabled. This is the broadest and most restrictive event coverage.

Trading Calendar

Allow New Trades on Monday

Default: **On**

Allows new EURUSD basket seeds during the module's built-in Monday trading hours.

Allow New Trades on Tuesday

Default: **On**

Allows new EURUSD basket seeds during the module's built-in Tuesday trading hours.

Allow New Trades on Wednesday

Default: **On**

Allows new EURUSD basket seeds during the module's built-in Wednesday trading hours.

Allow New Trades on Thursday

Default: **On**

Allows new EURUSD basket seeds during the module's built-in Thursday trading hours.

Allow New Trades on Friday

Default: **On**

Allows new EURUSD basket seeds during the module's built-in Friday trading hours.

Pause New Trade During End of the Year/New Year

Default: **On**

Blocks new EURUSD basket seeds from 24 December through 1 January inclusive.

Note — Weekday and holiday controls apply to new basket seeds only. Open baskets continue to be managed and may add grid positions or close normally.

AUDCAD — Identity and Execution

Identifies the integrated AUDCAD engine and controls direction, Hedge Mode, spread and permitted execution deviation.

Magic Number

Default: **463743598**

Unique identifier stamped on AUDCAD orders. Duelist manages AUDCAD positions only when both the resolved symbol and this Magic Number match.

Note — Keep it unique. Other AUDCAD trades with another Magic Number, including manual positions, are not included in Duelist's AUDCAD basket.

Order Comment

Default: **Duelist**

Text attached to AUDCAD orders for identification in the terminal. It is a label and does not replace the Magic Number.

Trading Direction

Default: **Both Directions**

Allows both BUY and SELL basket seeds, BUY seeds only, or SELL seeds only for AUDCAD. Existing baskets remain managed and may add grid positions.

Maximum Spread (points)

Default: **30**

Blocks both new AUDCAD basket seeds and additions to existing AUDCAD baskets while the current spread is above this threshold. Set 0 or less to disable this spread limit.

Note — This input is in broker points. It does not force the broker to fill an order at the displayed spread.

Hedge Mode

Default: **On**

When on, AUDCAD keeps its standard behavior and may open independent BUY and SELL baskets at the same time. When off, a new opposite basket cannot open until every position in the active directional basket has closed.

Note — The check covers AUDCAD positions matching the resolved module symbol and Magic Number, whether the active side contains one position or a grid. It does not force a close or suspend same-direction grid additions and basket management.

Maximum Slippage (points)

Default: **100**

Maximum permitted price deviation sent with AUDCAD trade requests. Actual execution remains subject to broker rules, liquidity and the available filling policy.

AUDCAD — Lot Sizing and Total Stop-Loss

AUDCAD has its own sizing profile and its own module-level floating-loss protection, independent of EURUSD.

Enable Auto Lot

Default: **On**

When on, Duelist calculates the AUDCAD base lot from the sizing balance and the selected risk preset. When off, Fixed Initial Lot is used.

Auto Lot Risk and Reference Balance

Default: **Medium**

Selects one of six AUDCAD balance references. Higher profiles increase the calculated base lot sooner.

Note — Duelist converts the AUDCAD sizing balance to a USD-equivalent when conversion data is available. This controls the base lot, not the maximum exposure of a later multi-position basket.

AUDCAD preset	Reference shown in MetaTrader	Relative sizing
Very Low	2500 per 0.01 lot	Smallest
Low	1500 per 0.01 lot	Lower
Low-Medium	1200 per 0.01 lot	Below default
Medium	1000 per 0.01 lot	Default
Medium-High	800 per 0.01 lot	Higher
High	500 per 0.01 lot	Largest

How Auto Lot steps — AUDCAD converts its sizing balance to a USD equivalent when possible. The calculated volume is $\max(1, \text{floor}(\text{sizing balance} / \text{reference})) \times \text{broker minimum lot}$, then normalized to broker limits. Below the first reference, the result is still one broker-minimum lot; different presets can therefore show the same lot over part of a balance range.

Fixed Initial Lot (when Auto Lot is disabled)

Default: **0.01**

AUDCAD base lot used when Auto Lot is off. The volume is normalized to the broker's allowed volume step and limits.

Exposure note — Auto Lot or Fixed Initial Lot defines the starting/base lot, not maximum basket exposure. AUDCAD has no public Maximum Grid Positions input; an existing basket may add positions and its order volumes may evolve, subject to broker and margin protections.

Total Stop-Loss

Enable Total Stop Loss

Default: **Off**

Enables a floating-loss limit across all AUDCAD positions owned by this module. When triggered, Duelist attempts to close those positions and temporarily pauses new AUDCAD entries.

Stop-Loss Measurement Mode

Default: **Account Currency**

Chooses a fixed account-currency threshold or a percentage-of-balance threshold for the AUDCAD total stop.

Currency Stop Loss (0 = off)

Default: **0.0**

AUDCAD floating-loss threshold in the account currency. Used only with Total Stop Loss enabled and Account Currency selected.

Percentage Stop Loss (0 = off)

Default: **0.0**

AUDCAD floating-loss threshold as a percentage of the current account balance. Used only with Total Stop Loss enabled and Percentage of Balance selected.

After a total stop — The dashboard can show RECOVERY WAIT. AUDCAD keeps new entries paused for at least 30 minutes while the module returns to a clean operating state.

Emergency margin protection remains active. Turning Total Stop Loss off disables only the user-configured threshold. AUDCAD retains an independent margin-safety guard and may close matching Duelist positions if account margin becomes unsafe.

AUDCAD profit management is preconfigured. The integrated module does not expose an Initial Profit Target input. Its exits are managed virtually by the EA, so MetaTrader, the trading account connection and Algo Trading must remain active; a stable VPS is strongly recommended for continuous operation.

AUDCAD — Trading Calendar

Weekday permissions and the optional year-end pause govern new AUDCAD basket seeds. All times and dates follow broker server time; existing baskets remain managed.

Allow New Trades on Monday

Default: **On**

Allows a new AUDCAD basket seed on Monday when all other strategy and safety conditions are satisfied.

Allow New Trades on Tuesday

Default: **On**

Allows a new AUDCAD basket seed on Tuesday when all other strategy and safety conditions are satisfied.

Allow New Trades on Wednesday

Default: **On**

Allows a new AUDCAD basket seed on Wednesday when all other strategy and safety conditions are satisfied.

Allow New Trades on Thursday

Default: **On**

Allows a new AUDCAD basket seed on Thursday when all other strategy and safety conditions are satisfied.

Allow New Trades on Friday

Default: **On**

Allows a new AUDCAD basket seed on Friday when all other strategy and safety conditions are satisfied.

Pause New Trade During End of the Year/New Year

Default: **Off**

When enabled, blocks new AUDCAD basket seeds from 15 December through 15 January inclusive.

Note — Existing baskets remain managed and may add grid positions.

Built-in AUDCAD NFP safety. AUDCAD blocks new basket seeds on the first Friday of every month and on the scheduled USD Nonfarm Payrolls broker-server day when calendar data is available. If calendar data is unavailable, the first-Friday safety remains active. Existing baskets, including grid management, remain active. The shared live calendar load window and Backtest Server-Time Convention also affect scheduled NFP-day detection.

Duelist uses the MetaTrader economic calendar for live/demo EURUSD operation and an embedded historical CSV calendar in the Strategy Tester. The impact switches in section 6 govern new EURUSD basket seeds.

Backtests use the Embedded CSV News File

The historical calendar is compiled into Duelist. Users do not need to install or update an external CSV for the supported tester period. The live/demo switch below does not disable the embedded tester filter.

Enable EURUSD Live/Demo News Filter

Default: **On**

Uses the live MetaTrader economic calendar to pause new EURUSD basket seeds around qualifying events. Turn it off only if you intentionally do not want live/demo news filtering.

News windows — Preselected EUR/USD categories use a fixed window from 400 minutes before to 5 minutes after the event; qualifying NFP events pause basket seeds for the entire broker-server day. The High, Medium and Low switches control those standard MetaTrader importance levels. A preselected event with another or unavailable classification may still participate. Existing baskets remain managed and may add grid positions.

Live Calendar Days Loaded Before and After Today

Default: **5**

Size of the live calendar window loaded on each side of the current day. A value of 5 loads recent and upcoming events far enough around today for the configured blackout logic.

Note — Values below 1 are invalid while the applicable news filter is active.

Print News-Filter Events in Journal

Default: **Off**

Compatibility input retained in product version 1.00. In the current build it does not enable additional event messages; essential calendar warnings and operational news-pause messages are handled independently. Leave it Off.

Backtest Server-Time Convention

Default: **New York Close / US DST**

Converts embedded UTC event times to the server-time convention represented by historical tester bars. Choose the convention that matches the broker data used for the backtest.

Available choices — New York Close / US DST (UTC+2 winter, UTC+3 during US DST), European EET/DST, fixed UTC+2, fixed UTC+3, or UTC. A wrong selection shifts the simulated news windows.

Calendar filtering is fail-open. If live data is unavailable or outside its loaded range, or a tester date is outside the embedded coverage, Duelist may allow new basket admission to continue subject to the other checks; it does not freeze trading. A source-load failure is reported at initialization, but an out-of-range runtime bypass may not add a Journal message in the current build. In product version 1.00, the embedded UTC range is 1 January 2020 through 20 August 2026. When a pause is active, the dashboard shows the available event label and countdown.

Dashboard and Appearance

Duelist's responsive dashboard combines account-wide context with EA-only module data, four analytics views and protected directional close controls.

Show Duelist Dashboard

Default: **On**

Shows the on-chart Duelist panel. The panel appears in live/demo trading and visual backtests, but is suppressed during optimization and non-visual tester runs.

Note — Turning the dashboard off does not disable trading.


Apply Duelist Chart Theme

Default: **On**

Applies Duelist's dark chart palette to improve dashboard readability. The previous chart colors are saved and restored when the EA is removed normally.

Note — This setting is independent of Show Duelist Dashboard. To keep the original chart appearance with no panel, turn both settings off.

Dashboard quick map



Schematic overview. The live panel automatically switches between full, compact and mini layouts according to the available chart size.

Account strip

Balance, equity, margin and current drawdown are account-wide values.

Lot Sizing Mode

Each module shows **AUTO • preset** or **FIXED • lot**, so the active sizing choice is visible without reopening Inputs.

Module cards

Counts, volumes, floating P/L and historical net profit include only the matching Duelist module.

Responsive layout

The mini layout keeps a live summary but hides manual controls and analytics. Enlarge the chart to restore them.

Analytics Views

LIVE

Default view

Shows account context, module status, symbol, historical net profit, current BUY/SELL exposure, floating P/L, Lot Sizing Mode, news notices and the last Duelist action.

EQUITY

Live session

Plots realized net plus floating P/L for Duelist only from the current dashboard session. It resets when the EA/dashboard is initialized and does not backfill an old live curve.

MONTHLY P/L

Last 12 months

Shows realized net results for owned Duelist positions by broker-server month, including profit, swap, commission and deal fees available from history.

STATS

EA only

Shows realized-balance maximum peak-to-trough drawdown and maximum stagnation. Floating drawdown is excluded from these historical statistics.

Controls and Status

The controls act only on positions owned by the selected Duelist module and direction. There is deliberately no account-wide Close All button.

Directional close buttons

Each module has separate **CLOSE BUY TRADES** and **CLOSE SELL TRADES** controls. The first click arms a five-second confirmation. Click the same button again before the countdown expires to send the close command.

Two-click protection. If the selected basket changes after the first click, Duelist asks for confirmation again. Clicking elsewhere, changing view or waiting longer than five seconds cancels the request. Always read the final button state and Last Action message.

RUNNING / ACTIVE

The module is initialized and operating. ACTIVE is normally used in the Strategy Tester.

NEWS PAUSE

New basket seeds are paused around a relevant event; open baskets remain managed and may add grid positions.

RECOVERY WAIT

AUDCAD is temporarily waiting after a protective close before it can accept new entries.

MANAGEMENT ONLY

EURUSD is managing existing exposure while new entry admission is intentionally blocked.

PROTECTING

A protection routine is attempting to close qualifying Duelist positions.

STOPPED / UNAVAILABLE

The module cannot currently open trades or did not initialize successfully.

DISABLED

The module switch is off.

TARGET REACHED

EURUSD has reached an internal operating target and is not accepting new entries.

Close feedback

Buttons can report **CLOSING**, **TRADES CLOSED**, **RETRY CLOSE**, **FIFO BLOCKED** or **CLOSE UNAVAILABLE**. After confirmation, Duelist retries in memory at approximately 650 ms intervals, for up to 15 seconds or 10 attempts without progress. Reinitializing or removing Duelist, or restarting the terminal, cancels an outstanding request. Broker FIFO restrictions, closed sessions, connection state, Algo Trading permissions and symbol freeze levels can prevent completion. Always verify that the requested side is flat; **RETRY CLOSE** means it was not fully closed.

Ownership boundary. A dashboard close command uses the module's symbol and Magic Number. Manual trades and another EA's positions are excluded only when their Magic Number differs. Never reuse a Duelist module Magic Number on the same symbol.

Live Trading and Strategy Tester

Use controlled settings and realistic data. A successful compilation or backtest does not guarantee future live performance or identical fills at another broker.

Live/demo checklist

1. Confirm the account is **MT5 Hedging**.
2. Attach Duelist to the broker's EURUSD symbol and verify AUDCAD is available if that module is enabled.
3. Confirm terminal connection, account trade permissions, the toolbar Algo Trading button and the EA's Common-tab permission.
4. Use distinct module Magic Numbers and avoid duplicating the same Duelist instance with the same identifiers.
5. Verify the dashboard's **Lot Sizing Mode** for each module before allowing new entries.
6. Start on demo or at the lowest suitable exposure and monitor the Experts/Journal tabs after initialization.

Strategy Tester checklist

1. Select Duelist and your broker's **EURUSD** symbol. M15 is the standard reference period.
2. For detailed validation, use **Every tick based on real ticks** where quality data is available.
3. Make sure both EURUSD and AUDCAD history can be loaded when both modules are enabled.
4. Select the **Backtest Server-Time Convention** matching the historical broker data.
5. Use Visual mode only when you need the dashboard; non-visual tests and optimizations suppress the UI for efficiency.
6. Keep symbol, period, date range, deposit, leverage, tick model and inputs identical when comparing two builds or settings.

Embedded news behavior. Backtests use the embedded historical CSV calendar even though live/demo uses the MetaTrader calendar. Version 1.00 covers 1 January 2020 through 20 August 2026 UTC. Outside that range the news filter is fail-open and may continue basket admission subject to the other checks; the runtime bypass may not add a Journal message. Results also depend on the selected tester-time convention.

Live fills can differ. Spread, slippage, commissions, swaps, symbol specifications, tick history, margin rules, FIFO restrictions and broker execution can all change the sequence and result of trades.

Troubleshooting, Risk and Support

Start with the exact dashboard status and the latest Experts/Journal message. The items below cover the most common operating questions.

“DUELIST CANNOT START” appears

Account mode

The account is Netting, Exchange or otherwise not reported as MT5 Retail Hedging. Move to a Hedging account or contact the broker. Duelist intentionally stops initialization.

The dashboard shows ALGO OFF

Permissions

Check the terminal Algo Trading button, the EA's Allow Algo Trading permission, account permissions and connection state.

AUDCAD is UNAVAILABLE

Symbol

Confirm the broker offers a tradable AUDCAD symbol and that its quote/history can be selected. Duelist supports normal broker prefixes and suffixes but cannot trade a disabled or missing instrument.

No new trades are opening

Admission

No trade can be normal for a selective strategy. Also check the module switch, direction, weekday, year-end filter, news pause, spread limit, recovery wait, margin, symbol session and Algo Trading status.

Other EURUSD trades are already open

Independent

Unrelated trades do not count as Duelist EURUSD basket positions when their Magic Number does not match. They may still reduce free margin or influence account-wide equity and drawdown values shown on the dashboard.

Analytics or close buttons are missing

Chart size

The panel has entered its mini responsive layout. Enlarge the chart or terminal window to restore the tabs and directional controls.

The EQUITY curve restarted

Expected

The equity curve is intentionally live-session only. Reinitializing Duelist, changing inputs, changing account or restarting the dashboard begins a new curve.

A close button reports FIFO BLOCKED or RETRY

Broker rule

The requested side could not be completed under the current account/symbol rules or market state. Read Last Action and the Journal, keep Algo Trading enabled and retry only after confirming the remaining positions.

Final Safety and Support

Positions opened with an old Magic Number remain

Identity changed

The current instance will not automatically adopt positions created with a different Magic Number. Restore the correct configuration or manage those positions deliberately.

Risk notice

Trading leveraged Forex products can result in substantial losses. Duelist does not guarantee profit, prevent gaps or eliminate broker execution risk. Total-stop thresholds and dashboard controls depend on market execution. Test the product on demo, choose exposure appropriate to your circumstances and never trade funds you cannot afford to lose. This manual is product documentation, not financial advice.

Support

When requesting help, include the product version, broker, account mode, symbol names, relevant Inputs and the exact Experts/Journal message.

mq15.com/en/users/mauroaugello