
BNT Rapid Copier

User Guide

LOCAL TRADE COPYING / MT4 + MT5

Configure the source. Control the receiver. Review copied results.



Supplied interface example. Visible profit and timing values are not expected results.

One product, two roles

Select Sender on the source account and Receiver on the copying account. Compatible terminals run on the same Windows PC or VPS and use the same local channel.

English edition. The supplied screenshots show the application header Local Copier, version 1.20. BNT Rapid Copier is the product name used in this guide.

CONTENTS

Find the right page

Quick start
The six-step first connection — 03

Choose the right environment
Local transport and MT4 / MT5 combinations — 04

Sender and connection
Role, channel and source filtering — 05

Symbols and lot sizing
Mapping, multiplier, fixed initial lots and limits — 07

Synchronization and filters
Entries, closes, SL/TP, pending orders and price checks — 09

Display and receiver
Scaling, source binding and receiver overview — 11

Profit Details
Copy-only metrics, currency and dates — 13

Activity and operating controls
Diagnostics, pause, stop and closing copied trades — 15

First-copy check and troubleshooting
Platform restrictions and common symptoms — 17

Illustrative examples
A filled sample dataset and a configuration reference — 19

Click a contents row or use the PDF bookmarks.

01 / QUICK START

Make your first connection

1. Install the platform-matching build on each terminal: EX4 for MT4, EX5 for MT5. Keep both terminals on the same Windows PC or Windows VPS, with access to the same MetaTrader Common Files folder.

2. Attach the EA to one source-account chart. Select **Sender**, choose a channel such as **BNT_01** and set the source-symbol and Magic filters you need.

3. Attach the compatible EA to a receiver-account chart. Select **Receiver** and enter the **same channel**. Confirm symbol mapping and lot mode before starting.

4. Review Synchronization settings, especially **Copy existing trades**. Apply and Save on each terminal. Configure while stopped.

5. Start the Sender, then start the Receiver. Confirm Sending / Copying, the expected source account and the target symbol. The receiver must be allowed to execute trades.

6. Use a demo account to verify a small eligible source entry, its copied direction and volume, then source-side close synchronization. Review Activity and Profit Details.

> **One sender per channel**
>
> Use a different channel for each independent source. Multiple receivers can follow one source when configured for the same local channel. Avoid configuring the same receiver account repeatedly on the same channel.

This copier executes real trading requests on the receiver when enabled. Local transfer does not guarantee identical fills, timing or results between brokers.

02 / REQUIREMENTS

Use a local environment

Requirement	What it means
Same PC or Windows VPS	Both terminals must be able to access the same Common Files location. Different physical computers do not share that local channel automatically.
Compatible builds	Use a matching MT4/MT5 copier protocol. MT4 to MT4, MT4 to MT5, MT5 to MT4 and MT5 to MT5 are the intended pairings; each terminal needs its own platform-specific build.
MT5 receiver account	Use a hedging account for receiver operation. Netting-account reception is not claimed by this guide; verify any different installed build before using it.
Trading and connectivity	The receiver needs trading permission, sufficient margin and a connected broker account. The sender must remain active to publish updates.
Local file channel	The supplied No_DLL interface and available implementation use native MQL shared-file transport. This is not a claim of pure shared-memory IPC. No relay server is needed for the local transfer.

Match the common-folder context


Run terminals where they can read and write the same MetaTrader Common Files folder. Different Windows users, isolated hosted environments, permissions or separate machines can prevent that. A matching channel name alone does not create a network link.

No DLL build

The supplied workflow uses native MQL local files. No DLL import or WebRequest whitelist is required for this local copy channel. A broker connection is still required to receive quotes and execute trades.

03 / SOURCE TERMINAL

Read the Sender overview



Actual Sender overview. Values are from the supplied screenshot.

Select Sender on the account whose eligible trades you want to publish.

Source Account
Check the masked account identifier, platform, currency and account type. This should be the intended source, not the receiver.

Channel
The example uses BNT_01. Enter exactly the same channel on the receiver. Use a distinct channel for a different source.

Symbols / Order filter
The screenshot publishes XAUUSD and shows All orders. The effective scope follows the configured source-symbol and Magic filters.

Source orders / Last sent
Use these as feed diagnostics. Zero source orders can be correct when no eligible orders exist.


Stop Sender
The button describes the next action. If Stop Sender is shown, the sender is running. Stopping publication is not a command to close receiver positions.

The receiver is configured separately

The source and receiver can be different MetaTrader platforms or brokers. The receiver mapping and sizing determine what trading requests it sends to its own broker.

04 / SETTINGS - CONNECTION

Set role and channel



Settings > Connection. The EA provides both Sender and Receiver roles.

Role
Sender publishes the source account. Receiver reads the selected channel and places the configured copied-trade requests.

Channel
Match both terminals exactly, including underscores and spelling. BNT_01 is an example, not a universal account key.

Apply and Save
Commit the edited settings. Returning to Overview without applying should not be treated as confirmation that a change is active.


One EA, two roles
Some receiver settings can remain visible while Sender is selected. They apply to receiver operation; there is no need for a separate user account or observation code.

Example	Correct pairing
Same local source	Sender BNT_01 -> Receiver BNT_01
Another independent source	Sender BNT_02 -> Receiver BNT_02
Different channel names	BNT_01 and BNT_02 do not pair with each other

Change the channel or source identity only while the copier is stopped and after reviewing any managed trades and stored source binding.

05 / SETTINGS - SYMBOLS

Map the exact symbols



Settings > Symbols. The screenshot demonstrates a broker suffix mapping.

Source symbol
Enter the actual source-market symbol, for example XAUUSD. It must match the source trade symbol.

Target symbol
Enter the receiver broker's actual symbol, for example XAUUSD.c. Confirm it is available and tradable in that terminal.

Different broker naming
Mappings can connect naming variants such as GOLD to XAUUSD, when they represent the intended instruments. A similar name does not prove identical contract specifications.

Apply on the receiver
Mapping is a receiver rule. Check the Overview mapping after Apply and Save.


Symbol mapping does not equal risk matching

Contract size, tick value, lot step and price precision can differ between brokers. Confirm the target specification and copied volume. Do not assume that 0.01 lots or a copied stop has identical monetary risk on both accounts.

The .c suffix is an example from the supplied screen; it is not a mandatory suffix or an instruction to rename all receiver instruments.

06 / SETTINGS - LOTS

Choose how lots are copied



Settings > Lots. The screenshot uses Multiplier mode with 1.00.

Multiplier
Initial target volume follows source volume x multiplier. Example: 0.10 x 0.50 = 0.05 lots before the receiver's lot-step rules.

Fixed lots
Sets the initial copied size for an eligible source position. Partial closes and later source-volume changes are reconciled relative to the recorded source basis; it is not a promise that the position can never change size.

Maximum lots
0 means no configured per-order maximum. An over-limit trade can be skipped rather than clipped to the limit. Check Activity instead of assuming the EA reduced the size.


Broker rules still apply
Minimum lots, maximum lots, step size, margin and execution conditions can prevent a requested volume from being opened.

Account currency does not set the lot multiplier

A cent account and a USD account can use different monetary units. The displayed currency conversion does not automatically scale copied lot sizes or make their exposure equivalent.

07 / SETTINGS - SYNCHRONIZATION

Choose synchronization rules



Shown configuration: entries, closes and SL/TP On; the other three options Off.

Copy entries
Permit eligible new entries and volume increases.

Copy closes
Follow configured source reductions and exits.

Copy SL/TP
Synchronize applicable stop-loss and take-profit changes, subject to broker rules.

Copy pending orders
Enable supported pending-order copying. Supported order types depend on the build and target broker.


Reverse copy
Reverse direction. Review how SL/TP is handled; it is not a hedge or profit guarantee.

Copy existing trades
Controls whether the first source snapshot is eligible for entry. Decide before first connection.

Existing trades Off means an already-open source position may not create a new receiver trade merely because you start the copier. A source-binding reset is a separate operation and should not be used to force duplicate entries.

08 / SETTINGS - FILTERS

Filter entries deliberately



Settings > Filters. Zero values in this example mean no configured threshold.

Source symbols
Restrict which source instruments are eligible. Use the source symbol, not the mapped receiver name. A blank filter means no symbol restriction in the reference implementation.

Source magic
Restrict eligible source strategies by Magic identifier. Empty means no Magic restriction. This is a filter on source orders, not a product password.

Maximum spread
An entry check in receiver-symbol points. Points are not always the same as pips. 0 disables this configured spread ceiling.


Maximum entry gap
An entry-price difference check in quoted price units. 0 disables this configured gap ceiling. It does not guarantee an eventual fill price.

A skipped entry is not always a connection failure

A valid local channel can still skip a trade because of filters, lot limits, price conditions, unavailable symbols or broker rejection. Read Activity to identify the applicable condition.

09 / SETTINGS - DISPLAY

Display and source binding



Settings > Display. The screenshot shows a panel scale of 100%.

Panel scale (%)
Adjust the panel for the chart area. Enlarge the chart before increasing scale. Avoid settings that hide buttons or cover essential account information.

Reset source binding
Clears the receiver's stored association with its source. It is not an ordinary refresh or a way to fix every skipped trade.

Before resetting
Stop copying and settle managed copied trades first, as the interface states. Review pending orders and any unresolved trade requests as well.

After resetting
The next start is handled as a new source connection. Recheck the channel and Copy existing trades setting before starting.

Preserve the working configuration

Do not delete local copier state or trade ledgers as routine troubleshooting. They help distinguish already-managed trades from genuinely new source entries.

10 / RECEIVER TERMINAL

Read the Receiver overview



Receiver overview and expanded Profit Details. The screen uses USC as the receiver currency.

Area	What to confirm
Source / Receiver account	The masked source identity and the actual receiver account are correct. The receiver is the account on which copied trades are executed.
Connection / Channel	Local file channel and the intended channel name. Copying indicates the current state; inspect Activity when a specific trade is skipped.
Copy Settings	The actual mapping and lot mode after Apply and Save. The small volume example is a sizing illustration, not a statement of equal account risk.
Timing / Today copies	Diagnostic observations for total time, execution and broker ping, plus the displayed copy count. They are not fixed execution benchmarks.

Stop Copying, Pause New Orders and Close Copied Trades are different operations. Read page 16 before using them on an active receiver.

11 / COPIED RESULTS

Open Copy Profit Details



Actual supplied Profit Details screen. Values are in the receiver's indicated currency, USC.

Click **Profit Details** on the receiver. Close x collapses the secondary panel without changing the main panel layout. The sender overview does not use this panel to report source-account profit.

Metric group	Meaning
Today's Profit / Total Copy Profit	Closed net results attributed to the receiver and current copier channel. These are not total profits for every trade on the account.
Floating P/L / Max Floating Loss	Current unrealized result and the most adverse aggregate floating observation retained for the copy scope. Historical floating loss cannot be reconstructed from closed profit alone.
Closed Deals / Win Rate / Profit Factor	Historical activity and result measures for eligible copied records. Interpret them together with the selected period and loaded history.
Copy Positions	Currently open positions recognized as belonging to this receiver's copier scope.

12 / PROFIT REFERENCE

Read dates, units and history

Control or concept	Reading guide
7 Days / 30 Days / All	Changes the available historical display period. A 7-day curve need not have activity on every day. All means the history available to the copier, not a guarantee of unlimited broker retention.
Cumulative Copy Profit	Adds eligible closed net results. The line can rise and fall. It is not the account equity curve and it excludes deposits and withdrawals.
Daily Summary	Groups the available copied results by receiver broker date. Click or scroll as supported by the installed build to inspect the available rows.
Trade Details	Opens the available per-trade copied records. Use them to reconcile the receiver history; exact columns and record counts follow the build.
USC versus USD	USC values are cents. 100 USC = 1 USD when USC is genuinely a USD-cent denomination. The sample +349.68 USC is about +3.50 USD, not +349.68 USD.
Broker date	Today and daily records follow the receiver's broker date. They do not automatically use your PC midnight, sender broker day or a chosen viewer time zone.

Unknown history is not confirmed zero

Missing or loading history, unknown costs or incomplete attribution should be checked before treating a metric as complete. Reconcile with the receiver's own trade history; do not fill actual records with demonstration data.

13 / EVENT READING

Use Activity to diagnose

Open **Activity** on the affected terminal. No Activity screenshot was supplied, so this page provides a reading guide rather than an invented capture of the application.

Event category	What it helps explain
Local feed / source state	Whether the sender is active, a channel snapshot is being published and the receiver can read the expected source.
Symbol / filter / volume	Whether an entry was excluded, the mapped symbol is unavailable, or the requested lot size does not meet a configured or broker limit.
Trading request / confirmation	Whether a request was submitted, accepted, rejected or still requires reconciliation. A sent request is not the same as a confirmed fill.
State / binding	Whether stored source association, trade ownership or local write permissions need attention.
Manual actions	Changes to running state, entry pause or closing copied trades. Review which terminal and account the action affected.

Record a useful support example

1. Note the platform and copier build on both terminals, their roles and channel names.

2. Record the source trade time, source and target symbols, lot mode, enabled synchronization options and the relevant Activity messages.

3. Include a redacted screen of the sender and receiver. Explain whether the issue affects a new entry, partial close, SL/TP, pending order or statistics.

> **Do not repeatedly resend an uncertain trade**
>
> Check the receiver's actual account history and pending requests first. Reattaching the EA or resetting state is not proof that an earlier request failed.

14 / OPERATING CONTROLS

Know the three controls

Control	Effect and practical use
Start / Stop Sender	Starts or stops publishing source updates. Stopping the sender does not itself close copied positions already held by receivers.
Start / Stop Copying	Starts or stops the receiver copy process. Stop is not the same as a command to close all copied positions. Existing trades remain subject to the actions actually enabled and running.
Pause New Orders	Blocks new copied entries while the running receiver continues applicable reduction, close and SL/TP synchronization. Existing pending orders can still have broker-side behavior; review them directly.
Close Copied Trades	An active trading action on recognized copier-owned trades, not a general close-all command for every strategy in the account. Confirm the affected account and channel, then verify closure results.
Close x in Profit Details	Only collapses the details panel. It does not stop copying or close trades.

A normal controlled shutdown

1. If you want to block new entries while keeping exit synchronization, use Pause New Orders on the receiver.

2. If you intend to close managed copied trades, use the dedicated close action and verify actual broker results, including pending orders and unresolved requests.

3. Stop the receiver and sender only when their continuing behavior is no longer needed. Keep the state files for later reconciliation.

Button labels normally describe the next action. A Stop Copying button therefore indicates that the receiver is currently running.

15 / VERIFICATION

Check the first copied trade

Check	Expected evidence
Same local channel	The configured Sender and Receiver show exactly the same channel and the intended source identity.
Eligible new source trade	The trade matches the symbol and Magic filters and was created after connection, unless Copy existing trades was intentionally enabled.
Target instrument	The mapped instrument exists on the receiver, is tradable and represents the intended contract.
Copied direction and size	The target direction follows normal or reverse mode. Requested volume follows the selected mode, lot step and permitted limits.
SL/TP and close	Applicable source changes are reflected when enabled and accepted by the receiver broker. Check actual order/position values, not just the running-state badge.
Statistics	Profit Details refers to the receiver, channel and indicated currency. The source-account result can differ from the copied result.

Cross-platform does not mean identical execution

The same source instruction can lead to different receiver prices, costs, availability or outcomes. Use compatible builds and verify each actual broker/account pairing before relying on it.

These checks describe operation, not an independent test certificate. The supplied screenshots show MT5; no native MT4 execution evidence or fixed-speed benchmark is established by this guide.

16 / TROUBLESHOOTING

Troubleshoot the workflow

Symptom	Check first
Receiver does not see the source	Same PC/VPS and Common Files context; exact channel; sender running; local read/write permission. Separate machines are not linked by this local channel.
Connected but no copied entry	Source order filters, Copy entries, Pause New Orders, Copy existing trades, symbol mapping, lot limits, spread/gap checks and receiver trading permission.
Old source position is not copied	Review Copy existing trades and when the source binding was established. Do not reset binding with managed trades just to force an entry.
Wrong symbol or no symbol	Use the exact target broker name; verify Market Watch availability, trading hours, contract size and price precision.
Trade size differs or is skipped	Multiplier/fixed initial lots, source basis, target minimum and lot step, maximum lots and available margin.
Source closed but receiver remains open	Copy closes enabled; both sides running; current source snapshot; broker permission and the actual close request/result.
Profit looks 100 times different	Check whether the receiver reports USC or another cent denomination. Currency units do not automatically change lot sizing.
Profit history or loss history seems incomplete	Check the available attributable receiver history and monitoring period. An observed floating-loss minimum is not a reconstruction of all past account risk.
Text or buttons are crowded	Enlarge the chart, reduce panel scale and verify the installed platform fonts.

Use MQL5 product comments or MQL5 private messages for Market-product support. Include redacted Activity information and the exact build versions.

APPENDIX A / SAMPLE DATA ONLY

A filled display example

Illustrative, not a live history

The following dataset was constructed to demonstrate a full daily summary. It is separate from the actual screenshot records and is never a substitute for missing real trade history.

Example day	Closed records	Net profit (USC)
Day 1	35	+45.20
Day 2	28	-18.35
Day 3	42	+62.48
Day 4	34	+37.90
Day 5	29	-25.10
Day 6	55	+184.75
Day 7	38	+62.80
Total	261	+349.68

This sample ends at **+349.68 USC** after both winning and losing days. The last sample day is **+62.80 USC**. These are presentation values, not claimed customer results.

Sample metric	Illustrative value
Closed records	261
Winning closed records	192 / 261 = 73.6% after rounding
Gross profit / loss magnitude	623.18 / 273.50 USC
Profit factor	2.28 after rounding
Current floating result / open copies	0.00 USC / 0

Maximum floating loss requires actual observation data. It cannot be inferred from this closed-P/L sample.

APPENDIX B / WORKSHEET

Keep a configuration record

Use this example as a format for documenting a setup. It is not a recommended risk profile or a promise that these values suit your accounts.

Field	Illustrative configuration
Product / interface	BNT Rapid Copier / Local Copier V1.20
Environment	Compatible terminals on one Windows PC or Windows VPS
Sender / Receiver	Source account / copying account; platform-matching builds
Channel	BNT_01 on both terminals
Source / target symbol	XAUUSD -> XAUUSD.c (example broker suffix)
Lot mode	Multiplier 1.00; Fixed lots 0.01 is unused while multiplier mode is selected
Maximum lots	0.00 in the screenshot means no configured per-order maximum
Copy entries / closes / SL/TP	On / On / On in the supplied synchronization screen
Pending / reverse / existing trades	Off / Off / Off in the supplied screen
Source Magic	Empty in the supplied screen; no Magic filter
Spread / entry gap	0 / 0.00 in the supplied screen; no configured ceiling
Panel scale	100% in the supplied screen

Terminology used in this guide

Local refers to terminals sharing a machine's native file channel. **Source** is the sender account. **Receiver** executes the copied trades. **Copy profit** refers to attributable receiver/channel results. **Sample data** describes a designed illustration, not verified account performance.

This guide uses the supplied English interface screenshots and available implementation notes. Exact behavior, supported order types and compatibility should be confirmed against the installed release.