EA Name : **Sanjib_Ghosh**
Copy Right 2017 @ Star Infotech Online Service
Contact : star.infotech.online@gmail.com

Input_Parameter :-

1. Use_ Order : **Buy / Sell / Both / None**
2. Start_Lot : 0.01
3. Take_Profit : …… pip
4. Stop_Loss : ……..pip
5. Slippage : 3
6. **Use_Martiangle** : No / Add / Multiply
7. Lot_Exponent : ……..
8. **Open_On_New Candle** : True / False ……...(if point 8 true, then point 9 false, or visa-versa)
9. **Use_Averaging** : True / False
10. Averaging _Step : ……pip
11. **Take _Profit_Avg** : ……pip
12. **Pending_Orders** : True / False
13. **Use_Trailing_Stop** : True / False
14. Trail _Start : 30 pip……. (trail starts from 'average trade price'of multiple trades)
15. Trail_Step : 10 pip
16. **Use_Partial_Close** : True / False
17. Partial_Close _Step : 30 pip ……..(close from 'average trade price' of multiple trades)
18. Partial_Close_Lot : 0.01
19. **Use_MaxQty_Odred** : True/False
20. Max_Trade_Buy : ……..
21. Max _Trade_Sell : ……..
22. **Use_Trading_Time** : True/False
23. Start_Hour :
24. End _Hour :
25. **Display_A/c Info** : True / False
26. Text_Colour :
27. Text_Size :
28. Pair_Rate_Size :
29. **Display_Close All_Button**: True / False
30. Close_All_Buy_Colour :
31. Close_All _Sell_Colour :
32. Close_All_Colour :

Explanation of Each Point

1. Use_ Order : Buy / Sell / Both / None

(i) Buy : EA will open Buy order, until max trades done & As per below rule.
(ii) Sell : Ea will open Sell Order, until max trades done & As per below rule
(iii) Both : Ea will open Both Order(Buy & Sell) at same time.
(iv) None : EA will not open any order, But when I open any order **manually** from **any terminal** EA will work on it.

2. Start_Lot : 0.01

Ea will open any Starting buy or sell or both order with lot size 0.01

3. Take_Profit : 50 4. Stop_Loss : 100

After placing any order, Ea will quickly setup TP : 50 pips and SL : 100 pips
But
If **Use_Order : None**,
If I place any order **manually** from any terminal, EA will also setup TP : 50 pips and SL : 100 pips.

5. Slippage : 3

Maximum slippage can happen 3 pips. Otherwise, order will not open.

6. Use_Martiangle : No / Add / Multiply 7. Lot _Exponent : 0.01 or 2

(i) No = Lot size of all trades will be same. That means, 1st trade lot size = subsequent trades lot size.

(ii) Add = if lot_exponent is 0.01, then Lot size of 2nd trade onwards will **add** 0.01 with previous lot.
That means, 1st. Trade Lot Size = 0.01 (Start_Lot)
2nd. Trade Lot Size = 0.01 + 0.01 = **0.02**
3rd. Trade lot Size = 0.02 + 0.01 = **0.03**
4th. Trade lot Size = 0.03 + 0.01 = **0.04**
5th. Trade lot Size = 0.04 + 0.01 = **0.05**

(iii) Multiply = if lot_exponent is 2, then lot size of 2nd. Trade onwards will **multiply** 2 with previous lot.
That's mean - 1st. Trade Lot size = 0.01 (Start_lot)
2nd. Trade Lot size = 0.01 x 2 = 0.02
3rd. Trade Lot size = 0.02 x 2 = 0.04
4th. Trade Lot Size = 0.04 x 2 = 0.08
5th. Trade Lot Size = 0.08 x 2 = 0.16

8. Open _On_New_Candle : True / False

Ea will continuously open new Buy order or new Sell order on every new candle start.

But If Use _order : Both or None, then open_on_new_candle = **False**.

9. Averaging : True 10. Averaging_Step : 40

Ea will continuously make new buy order or sell order after every 40 pips from previous trade.

Example - If 1st. trade is Euro/usd Sell at 1.05200 (open _on_NewCandle = False)
2nd. Trade euro /usd sell at 1.05600
3rd. Trade euro/usd sell at 1.06000
4th. Trade euro/usd sell at 1.06400 and so on…until SL hits or Max_trade done.

11. Take Profit_Average : 30

When EA open any 1st. Trade 1st time, EA will setup initial TP & SL as per above point **3** & **4** (above).
But when EA opens 2nd Trade onwards -
Ea will change TP every time (no change SL).
EA will make average trade price of multiple trades and then set TP 30 pip distance from there.

Example : -
1st. trade Sell euro/usd **0.01** at **1.05200** …. setup TP : 1.04700 & SL 1.06200 (tp=50 sl=100)
2nd trade Sell euro/usd **0.02** at **1.05600**
(Average selling price of above 2 trades is **1.05467**)
Now EA will change TP of Both trades to (1.05467 – 30 pips) = **1.05167**
(change TP from 1.04700 to 1.05167)
3rd. trade sell euro/usd 0.04 at **1.06000**
(average selling price of above 3 trades is : **1.05771**)
EA will change TP of all 3 trades to (1.05771 – 30 pips) = **1.05471** **(it will continue like this…)**

12. Pending Orders : True / False

true : All future trades will be open by EA, will place as pending orders.
false : All future trades will be open by EA automatically execute when reach appropriate price. No pending order will be placed.

13. Use_Trailing Stop : True 14. Trail_Start : 20 15. Trail_step : 5

When 1 trade is open :-
If 1st trade Sell Euro/Usd 1.05200 …….TP : 1.04700, SL : 1.06200 (tp= 50, Sl= 100)
Now if move profit side, 1st. 20pip profit move ……SL change to cost to cost
Then, every 5 pip profit move …….. SL change to every 5 pip to lock profit.

When multiple trades are open :-
1st trade sell 0.01 at 1.05200 ……Sl : 1.06200 (100pip)
2nd trade sell 0.02 at 1.05600……Sl : 1.06200
3rd. trade sell 0.04 at 1.06000 ……Sl: 1.06200
(Average selling price of all 3 trades = **1.05771**) >>> trailing stop will work on it.
When price come back to (1.05771 – 20 pip) = 1.05571, All trades SL will change to cost : 1.05771.

After that, every 5 pip profitable move, SL will change 5 pip continuously to lock the profit.

16. Use_Partial_Close : True 17. Partial_Step : 15 18. Partial_Lot : 0.01

When 1 trade is open :-

On every 15 pip profitable move, EA will close 0.01 position automatically.
If Lot size is minimum (0.01), then will not close any position.

When multiple trades are open :-

1st trade sell 0.01 at 1.05200 …….Sl : 1.06200 (100pip)
2nd trade sell 0.02 at 1.05600……Sl : 1.06200
3rd. trade sell 0.04 at 1.06000 ……Sl: 1.06200
(Average selling price of all 3 trades = **1.05771**)

When price come (1.05771 - 15pip)= 1.05621, ……0.01 position will be closed from last trade.
When price come (1.05621 - 15pip)= 1.05471 ……0.01 position will be closed from any last trade.
When price come (1.05471 - 15pip)= 1.05321 ……0.01 position will be closed from any last trade.
Will continue like this….. until TP or SL hits.

Other points are ok,
So, no need to explain, I think.

==========

Restriction of Use :-

1. I will put an account no on .mql4 file. EA will work on that account only.
2. I will mention Expiry Date on .mql4 file. Ea will not work after that date.
3. Message Will Display on Screen (no pop up window) : "**Your subscription has expired, pls renew by calling : +919732065498**"

Account Info :- (Display on MT4 Screen, Left Side)

Account Balance :
Total Equity :
Floating Profit /Loss (this pair) :
Total _Lot_Buy (this pair) :
Average Buy Price of All trades (this pair) :
Total_Lot_Sell(this pair) :
Average Sell Price of All Trades (this pair):
Spread : Remaining Bar Time :

1.05200 <<<< rate will display hare like this. (It will also Blink, red=decrease, Green=increase)

“**Close_Buy**”, “**Close Sell**”, “**Close All**”

It will display like below image.



Those Button will close only that pair, in which, EA is attached.
It will not close other pair buy sell.

Your suggestion on any point to improve will be wel-come.
