

EA Name : Trade Manager

EA Type : MT4

Input Parameter :-

- 1. EA Work On : All Pairs / Single Pair
- 2. TP :Pips
- 3. SL :Pips
- 4. Manual Modify Allowed : True / False

***** TRAILING STOP *****

- 5. Trailing Stop : True / False
- 6. 1st Trail Starts On : Pips
- 7. 1st SL Move / Modify at Cost + : Pips

- 8. Next Trail Step on Every :Pips
- 9. SL Move/Modify :Pips

***** PARTIAL CLOSE *****

- 10. Partial Close : True / False
- 11. Partial Type : Fixed / Floating

IF - "**FIXED**"

- 12. 1st. Partial Close On : Pips
- 13. 1st Partial Close Lot : % of Total Lot Size

- 14. 2nd. Partial Close On : Pips
- 15. 2nd. Partial Close Lot : % of Total Lot Size

- 16. 3rd. Partial Close On : Pips
- 17. 3rd. Partial Close Lot : % of Total Lot Size

IF - "**FLOATING**"

- 18. Partial Close Starts On : Pips
- 19. Partial Close Lot : % of total Lot Size

|| DESCRIPTION POINT WISE ||

First of all, This EA will not open any Trade automatically.
It will just manage all the trades, which are open manually from any MT4 terminal – like Desktop MT4 / Mobile MT4 etc.

Point No 1 : (All Pairs / Single Pair) : –

Suppose, EA Attached in EUR/USD Pair chart.

If “**All Pairs**” Selected – Then Not only Eur/USD, It will work on all orders open manually in any pair.

If “**Single Pair**” Selected – Then It will only work on that pair orders, In which, EA is attached. That means, It will work on EUR/USA pair Orders only.

Point No 2 And Point No 3 : (TP & SL) :-

As soon As, EA Finds any New Order open manually from any MT4 Terminals, It will set TP & SL as per data given.

Point No 4 : (Manual Modify Allowed – True / False) :-

If - TRUE :

Initially, EA will Set TP / SL as per input data in point 2.

But If I want to modify TP /SL manually in any price, EA will allow that.

EA will not interfere on my Manual Modification of TP /SL.

IF – FALSE :

Initially, EA will set TP / SL as per input data.

And EA will not allow to modify it manually.

If I try to modify TP/SL, then it will again set it as per his rules given in point 2.

Point No 5 : (Trailing Stop : True /False) :-

If False - “ Trailing Stop” process will be Inactive.

If True - “ Trailing Stop” process will be Active and work as per rules.

Point No 6/7 : (1st Trail Starts on / 1st SL Move) :

Suppose –

1st Trail Starts On : **15 Pips**

1st SL Move / Modify at Cost + : **1 Pip**

Then,

As soon as, Price moves to 15 Pips Profit,

SL will be modified by the EA to COST + 1Pip

Point No 8/9 : (Next Trail Step on Every / SL Move/Modify) :-

Suppose,

Next Trail Step on Every : 20Pips

SL Move/Modify : 10 Pips

If price moves First 15 Pips + Next 20 Pips = 35 Pips profit,

SL will be modified by EA to – First (Cost+1Pip) + Next 10 Pips = Cost +11Pips.

Again, If price moves 35Pips + 20Pips = 55 Pips Profit,

SL will be modified by EA to : Cost + 11Pips +10Pips

It will continue like that, until TP or SL Hits.

Point No 10 : (Partial Close : True / False)

If True, Then this process will be Active

If False, Then this process will be Inactive.

Point No 11 : (Partial Type : Fixed / Floating)

If “Fixed”, It will follow “Fixed” Rules

If “Floating”, It will follow “Floating” Rules.

Point No 12/13/14/15/16/17 :

Suppose,

I have Buy Eur/Usd with Lot Size : 1

1st. Partial Close On : 15 Pips

1st Partial Close Lot : 25 %

2st. Partial Close On : 30 Pips

2st Partial Close Lot : 25 %

3st. Partial Close On : 50 Pips

3st Partial Close Lot : 25 %

When price moves 15Pips profit from Cost, EA will close 25% of original lot size, that is 0.25

When Price Moves 30 Pips profit form Cost, EA will close another 25% of Original Lot size, that is 0.25

When Price Moves 50 Pips profit form Cost, EA will close another 25% of Original Lot size, that is 0.25

Total 3times partial closes. Remaining will be left. No more Partial close.

Point No 18 / 19 : (Partial Close Starts On / Partial Close Lot)

Suppose,

Partial Close Starts On : 15 Pips

Partial Close Lot : 25%

That's mean, On every 15Pips Profit move,
EA will continuously close 25% of Original Lot Size.

Note : Suppose, One trade is open in Eur/Usd and EA is working on it as per rules. Now If I open another Trade in same Pair Eur/Usd. Then –
EA will follow each new trade each new rule policy. EA will not combine it any way.

