

Common	Inputs
Variable	Value
ab ~	DEFAULT STRATEGY TESTED on M15
ab ~	DEFAULT STRATEGY USES D-ENTRY
ab ~	D-ENTRY ONLY USES MAX of 3 SYMBOLS
ab ~	TO USE OTHER STRATEGIES TURN D-ENTRY FALSE
ab ~	
ab ~	TO SEMI AUTO TRADE DISABLE AUTO OPEN IN SETTINGS BELOW
ab ~	
ab ~	CLICK THE BUTTONS TO OPEN TRADES WHILE BACKTESTING
ab ~	YOU MAY NEED TO SLOW THE BACK TEST DOWN TO CLICK IT
ab ~	
o1 EA OnTimer MS	1000
ab ~	
ab Comment	Market Crusher
o1 Magic Number	333555999
🔗 Auto Draw Chart	true
🔗 Use AI Sound	true
🔗 Use Button Verification	true
o1 Button Font Size	8
🗑 Choose AI Language	Arnold Schwarzenegger
ab ~	
🗑 Choose Lot Sizing	Fix Lot
¼ X Balance(Auto Lots)	1000
½ X Lot for X Balance(Auto Lots)	0.01
¼ Fix Lot	0.01
ab ~	
¼ X Balance(Auto Lots) D3	1000
½ X Lot for X Balance(Auto Lots) D3	0.01
¼ Fix Lot D3	0.01
ab ~	
ab ~	High % Opens Less trades - Low % Opens More Trades
ab ~	5% to 95% - Never 0% or 100%
¼ Percent of Symbols Trending	95
ab ~	
ab ~	Symbol Correlation
🔗 Correlate to Strongest Symbol	false
🔗 Reverse Correlate	false
ab ~	
ab 28 Forex Symbols	AUDCAD,AUDCHF,AUDJPY,AUDNZD,AUDUSD,CADCHF,CADJPY,CHF
ab Symbols to Trade(Min 2 - Max 28)	AUDJPY,GBPJPY
🔗 Use Auto Suffix	true
ab ~	
o1 History LookBack Max(199)	199
o1 Trend MA Period	10
🗑 MA_Method	Simple

We understand this EA is very complex & hope this guide will navigate you through all of the exciting features to help you be a profitable trader for years to come! Happy Trading. *The Destroy the Odds Team*

This is the milliseconds for initiating a trade. If it is too low multiple trades may open at one time.

The Magic number is very important. Make sure you do not have other instances of this EA or any other EA with the same magic number.

Use AI Sound to turn Off or On Voices. Use Button Verification False to open your trade Immediately when clicking buttons when trading from the buttons on the chart.

Fix Lot will open the same lot size regardless of balance.

Changing this to Auto Lot will adjust your lot size according to balance.

X Balance Auto Lots is the amount of Balance for every Lot size in next setting if Auto Lots has been selected.

Fix Lot is the lot size when using the Fix Lot selection.

VERY IMPORTANT... This is one of the MAIN FUNCITONS of this EA. You determine what a Trending or Ranging market is here by adjusting the percentage of Symbols Trending. 95% means all of the symbols must trend to allow trades. 1 to 5% means its always Trending & Allowing Trades.

Symbol Correlation if true will force all symbols to trade in the same direction of the Strongest Trending Symbol. If Reverse Correlation is true also it will force all other symbol to trade opposite.

Symbols to Trade.... Enter the symbols you want to trade here separated by a comma. Never have an extra comma nor a comma at the end of the string of symbols or it will be very bad.

History Look back is the number of bars the EA will analyze for the trend. Max is 199.

VERY IMPORTANT.. Trend MA Period & MA Method is the Moving Average defining your Trend.



Load
Save

OK Cancel Reset

Variable	Value
ab ~	These 2 Close Options are Non Fifo
1/2 Close Equity Points Profit	50
→ Close Profit Trade Only	false
ab ~	
1/2 Close Equity Points Loss	0
→ Close Loss Trades Only	false
ab ~SL Pips	
1/2 SL Pips_A	0
1/2 SL Pips_B	0
1/2 SL Pips_C	0
1/2 SL Pips_D	0
1/2 SL Pips_Butons	0
ab ~TP Pips	
1/2 TP Pips_A	0
1/2 TP Pips_B	0
1/2 TP Pips_C	0
1/2 TP Pips_D	0
1/2 TP Pips_Butons	0
1/2 Trail Start(0 to deactivate)	0
1/2 Trail Step	1
1/2 Trail Above BreakEven	1
1/2 Virtual TP Pips	0
01 Minutes Stagnant to Disable Virtual TP	0
1/2 Symbol Profit Points TP	0
ab ~	
01 Delay A(Minutes)opening after prev open A	720
01 Delay B(Minutes)opening after prev open B	720
01 Delay C(Minutes)opening after prev open C	720
01 Delay D(Minutes)opening after prev open D	10
01 Delay Grid(Minutes)opening after prev open (A,B,C,D Grids)	720
ab ~	
ab ~	Define How many Bars are in the Trend
01 X Bars in the Trend(0 is Always Trending)	50
ab ~	Define Trend Range to Open Trades
01 More than X Bars Open	50
01 Less than X Bars Open	500
ab ~	
ab ~ Auto Open	AUTO OPEN SETTINGS - ALL FALSE FOR SEMI AUTO
ab ~	
☰ Choose ENTRY TYPE Initial	LONG or SHORT
→ Auto Open All Symbols Above X Bars Open(A)	false
→ Auto Open Only Strongest Symbol(B)	false
→ Auto Reversal(C)	false
ab ~	

Close Equity Profit Points will close the combined total of profit points for the magic number on this EA. If you have X number of trades open and the Equity for these trades reaches the points profit here all of the trades will close but it will not obey FIFO broker rules. You must have a **NON Fifo Broker** to use this setting. Close profit trade only will only close the winning trades but leave the losing trades open. Close Equity Points Loss does the same thing but for Equity loss.

The SL pips & TP pips shown here is for setting individual Stop Loss and Take Profit for each type of entry position, A or B or C or D and even an SL or TP for when you click a button to open a trade.

Trail Start, Trail Step, Trail Above Break Even applies to all Entries.

Virtual TP is a Take Profit method that works per symbol. This Obeys FIFO Rules and will work with heavily regulated brokers that require FIFO. Minutes Stagant is if you want to target each individual symbol Virtual TP and if it has not closed yet it will revert to Equity Points to calculate all of the trades to Take profit on Equity Points. Symbol Profit Points is another Type of VTP.

Delay after Previous Open will define how many minutes you want to delay the EA from opening another trade for each of the AUTO entry settings A or B or C or D. Delay Grid will work only if you enable the grid setting.

VERY IMPORTANT HERE. This is where YOU define how many bars are in a trend based on the Trend Moving average you set earlier in these setting and based on the percentage of symbols trending setting. Define Trend Range is the Range of Bars that the EA will allow a trade to open.

Long or Short Allows you to trade only Long or Short or Long and Short.

Auto open A True will open all Trending Symbols within the Range that was set.
Auto open B will only open the strongest trending Symbol.
Auto Open C will open when the candle crosses the Trend Moving Average.

Load

Save

OK

Cancel

Reset

MARKET CRUSHER PRO 1.9

Common Inputs

Variable	Value
ab ~	LOAD ONLY 2 or 3 SYMBOLS IN SYMBOL SETTING FOR D-ENTRY
ab ~	TURN THIS FALSE TO USE A or B or C ENTRY
🔗 Auto Open Correlation Gap(D)	true
🔗 Invert Correlation Gap(D)	false
🔗 Invert 3rd Symbol	false
1/2 Correlation Min Gap Pips	1
1/2 Correlation Max Gap Pips	10
1/2 Correlation Min Bars	1
1/2 Correlation Max Bars	2
01 Correlation Gap 3rd symbol Open on X Minutes Stagnant	1440
ab ~	
🔗 Use Strongest Symbol(C)	false
🔗 Use Range(C)	true
🔗 Invert (C) Trade	false
01 Consecutive Bull/Bear Candles Open	1
ab ~	
ab ~	Optional Grid Settings
☰ Choose Grid Distance	Average Price
01 Open Grids On X Minutes Stagnant(0 to deactivate)	0
1/2 Minimum Grid Distance	50
01 Max_Grid	10
ab ~	
ab ~	
ab ~	These Settings Work Only on Auto Trading
ab ~	Only for Entry A or B or C or D - Not Combined
01 Max Open Symbol Count	28
01 Allow X Trades per Symbol to Open	1
01 Allow X Trades to Open(symbol 3 on D)	10
🔗 Allow Hedging(for Entry A or B or C or D)	false
ab ~	
🔗 Invert Trades by Trade Count	false
01 Less than X Trades Invert True More Invert False	5
ab ~	
🔗 Invert Trades By Trend Bar count	true
01 Less than X Bars Invert True More Invert False	100
ab ~	
01 More than X Trades Reduce Equity TP	0
🔗 Block trade if Symbol is in loss.	false
ab -	

Auto Open Correlation Gap True will only work with 2 or 3 symbols. Do not have more than 3 symbols in the symbol setting. The first 2 symbols should be heavily correlated. The 3rd symbol is optional and is usually a cross pair. Example EURUSD,GBPUSD,EURGBP. **Invert Correlation false** will trade buys above the trend line and sells below. True will reverse this. **Invert 3rd Symbol true** open buys above the trend line and sells below. True will reverse this. Correlation Min Gap pips is the min pip distance from the trend line to open. Max gap pips is the maximum. Min Bars and Max bars is the same concept but counts the bars in the trend. Correlation gap 3rd symbol X minutes will only open the 3rd symbol after this X number of minutes.

Use Strongest Symbol is only used for the C Auto Entry Setting. If true it will take the MA cross for the Strongest Symbol that crosses over the MA to take the Strongest Reversal. If set Strongest symbol false and use range true it will take these reversal trades on ALL of the symbols that cross the MA instead of just 1 at a time. **Invert C trade** is to take the trade in direction of the previous trend when the candle crosses the MA. **Consecutive Bull/Bear Bars** will only open when X Bull Bars = Buy or C Bear Bars= Sell and this is for A or B or C Entry. **Optional Grid Settings....** Open Grids on X minutes Stagnant. 0 Grids never open. 1 grids can open after 1 minute. 60 minutes then Grids can open after 60 minutes. 1440 minutes then grids can open after 1 day. Grid Distance is min distance for grids when using Grid distance in drop down(default is using Average price) Max Grid is the max number of grids allowed.

Max Open Symbol Count is the total number of symbols allowed to be open at any one time. **Allow X trades per Symbol** to open will allow up to this number of trades for each symbol to be open at any one time. **Allow X trades to open(Symbol 3 on D entry)** is ONLY for D Entry Open when using a 3rd symbol. It will only allow up to this number of 3rd symbol trades. **Allow hedging true** will allow all symbols to hedge when they get a signal to open.

VERY IMPORTANT HERE. Pay attention or you will get confused here. **Invert Trades by trade count** or bar count will invert the trading entry after X number of trades or bars open. If these are both false the signal is always following the trend. **If true it will start with mean reversion and when it reaches the target trade count or bars count in the trend it will follow the trend.**

More than X trades reduce Equity TP. If 0 it always uses Equity TP points. If you set this to a number it will count how many trades you have open and calculate Equity TP points per trade until this number is reached and then revert back to the Equity Points value for all trades together.

Load

Save

OK

Cancel

Reset

Auto GMT (False will use broker time)	true
EA GMT Offset	3
Start Hour	1
Start Min	0
End Hour	23
End Min	55
-Minute Filter	
Start Minute Filter	0
End Minute Filter	59
-	
Close on X Hour	false
Close X Hour	0
Close X Minutes	0
-	
Close All Trade Outside Trade Hours	false
-	
TradeMonday	true
TradeTuesday	true
TradeWednesday	true
TradeThursday	true
TradeFriday	true
TradeSaturday	false
TradeSunday	true
-	
-	Disable with 0
-	This Close is Non Fifo
Close Friday Hour	0
Close Friday Min	0
-	
Volatility Settings	
Period	current
Period 1	5
Period 2	20
Volatility Size	1
Use Auto Volatility Filter	false

Auto GMT will force your time to work with the EA GMT offset. This is not what you may be used to so please message us for clarification if you do not understand. We set this to GMT3 for Daylight Savings time in the Spring and GMT2 for DST in the fall. This can change if USA gets rid of DST in 2022. Please pay attention to this every spring and fall.

**Start hour and Start Min is when the EA will look for trading entries.
End hour and End Min is when the EA wil stop looking for trading entries.**

Start minute Filter and End Minute filter will only look for trades each hour between these start and ending minutes each hour. Maybe you want to trade 25 minutes to 35 minute in each hour and not trade all through every hour.

Close on X hour and X minutes will close all open positions that day on this hour/minutes.

Close All trades Outisde Trade hours will close all open positions as soon as the End hour and End Minutes is reached for that day.

Trading Days. Set true to trade that day. Set false to not trade that day.

Close Friday hour and Min will close all open positions on Friday on this hour and minute. 0 disables this.

Volatility Settings..... This is the setting to adjust the sensitivity for the Volatility Indicator you see on the chart. When the Buttons change from dark to bright it means that symbol is in high volatility for that timeframe. Setting the Period to current it will detect volatility on your current time frame. Use Auto Volatility Filter will filter your auto trading entries to only allow the trade to open when it is in high volatility if this is set to true.

Load

Save

OK

Cancel

Reset