

Variable	Value	Description
hint1	===== trade entry settings =====	
EnableMM	true / false	enable MMRisk function
MMRisk	3.0	risking 3.0% of the account equity
FixedLot	0.01	fixed position size
TPOnSLRatio	1.5	if SL = 10 pips, then TP = 10 x 1.5 = 15
SoundAlert	true / false	enable sound alert for "positon-open"
SoundName	alert.wav	the sound file to use as sound alert
PushAlert	true / false	to enable PushAlerts available in MT4
EmailAlert	true / false	to enable EmailAlerts, sent to email
AllowMultipleSignal	true / false	to enable multiple signals at a time
MinTimeGap	15	minimum time in between 2 signals
PositionLimit	3	maximum number of opened positions
OpenReverse	true / false	the EA will open a reversed position
OpenHedged	true / false	the EA will open 2 hedged positions
SetSLTPOnEntry	true / false	SL and TP will be set automatically
AddSpreadToSLOnSellEntry	true / false	SL+spread for SHORT positions
MinSLToOpenTrade	5.0	minimum SL to open trade
MaxSLToOpenTrade	100.0	maximum SL to open trade
ProfitReached	10.0	if position is in 10.0+ pips profit, then :
ProfitLock	2.0	move the SL to 2.0 pips profit ...
hint2	===== indicator settings =====	
hint21	===== bollinger settings =====	
BBPeriod	60	internal BB indicator settings
BBDeviation	3.5	internal BB indicator settings
BBApplied	Close price	internal BB indicator settings
MinMiddleLineDistance	1.0	signal valid only if min.1.0 pips from SMA
hint22	===== psar settings =====	
PSARStep	0.01	internal PSAR indicator settings
PSARMaximum	0.05	internal PSAR indicator settings
PSARTrailing	true / false	move trailing stop with PSAR ...
hint3	===== time settings =====	
TimeFilter	true / false	limit the time period when the EA works
StartHour	09:00	internal PC clock - start hour
StopHour	15:00	internal PC clock - end hour
hint4	===== other settings =====	
MagicNumber	32987	change this number to any you like ...

TradeComment | mechanic | change the text to anything you need ...

Antonin Skaryd

FUTURE ENTERPRISE

23.09.2015