

EA COPY TRADE USER GUIDE

How to Install

- 1 Install two MetaTrader platforms on one computer: one as the Master and one as the Slave.
- 2 Install **MASTER EA (master.ex5)** on the Master terminal and **SLAVE EA (client.ex5)** on the Slave terminal.
- 3 Attach the EA to the appropriate chart and enable AutoTrading.
- 4 All transactions opened, modified, and closed on the Master account will automatically be copied to the Slave account.


Input Parameters

Parameter	Description
ReadIntervalMs	Interval (milliseconds) for the Slave EA to read data from the Master. Lower values provide faster copying.
ReverseMode	Reverse trading direction. BUY becomes SELL and SELL becomes BUY.
CopyCurrentTrades	Copy currently open trades when the Slave EA starts.
LotMode	Lot calculation method. 'Percentage of Master Lot' means the Slave lot size is based on the master's lot.
FixedLot	Use a fixed lot size when Fixed Lot mode is selected.
LotPercent	Percentage of the Master lot to use.
MaxLot	Maximum lot size allowed.
MinLot	Minimum lot size allowed.
SymbolSuffix	Automatically detect or specify broker symbol suffix.
SymbolPrefix	Automatically detect or specify broker symbol prefix.
Symbol Map	Manual symbol mapping for brokers with different symbol names.
CopySL	Copy Stop Loss from Master.
CopyTP	Copy Take Profit from Master.
Slippage	Maximum allowed slippage during order execution.
CloseOnMasterClose	Automatically close Slave trades when the corresponding Master trade closes.
ShowPanel	Show or hide the information panel.
Panel Background Color	Background color of the EA panel.
Text Color	Text color of the EA panel.

HOW TO INSTALL AN EA ON METATRADER 5


1 Copy and paste the EA file into the following Experts folder:

Click the **File** menu in the upper-left corner of MetaTrader, then select **"Open Data Folder"**. Open the **MQL5** folder, then open the **Experts** folder.



2 Restart MetaTrader, then press Ctrl + N to display the Navigator window.


Next, drag the EA from the Expert Advisors folder on the left panel to the chart.



3 Enable Algo Trading



Open the **Common** tab in the EA properties window and check **"Allow Algo Trading"**



Important:

Make sure the Algo Trading button on the toolbar is green. If it is red, click it to enable Algo Trading.

