





## INFINITY TradeUtility EA for TrendLine PRO

As soon as you purchase the utility, you can install it from Market/Purchased (Purchases) folder:



You can activate updates of the purchased programs the same way from Market/Purchased (Purchases) folder:



First, make sure you have activated your account in MQL5 Community:

Options

Server

Charts

Trade

Expert Advisors

Events

Notifications

Email

FTP

Community

Sign Out

Specify your MQL5.community account details to be able to buy trading robots in the Market, copy traders in the Signals service and place orders for the development of trading applications in the Free Market.

MQL5.community is an official community of developers and service providers for trading platform.

Login:

Password:

protected with encryption

If you don't have an account, please register.

To test and use the EA, you should download all the history for the traded symbol, which is available at your broker. For most trading systems that use indicator signals, it is enough to download a minute or tick history. Other periods will be recalculated by MetaTrader 4/5 independently.

History Center: EURUSD,M1

**press F2**

Symbols:

- EURUSD
  - 1 Minute (M1)
  - 5 Minutes (M5)
  - 15 Minutes (M15)
  - 30 Minutes (M30)
  - 1 Hour (H1)
  - 4 Hours (H4)
  - Daily (D1)
  - Weekly (W)
  - Monthly (MN)

Database: 650056 / 7830966 records

Time	Open	High
2020.10.06 14:13	1.17794	1.178
2020.10.06 14:12	1.17809	1.178
2020.10.06 14:11	1.17807	1.178
2020.10.06 14:10	1.17800	1.178
2020.10.06 14:09	1.17814	1.178
2020.10.06 14:08	1.17816	1.178
2020.10.06 14:07	1.17815	1.178
2020.10.06 14:06	1.17802	1.178

In MetaTrader 5 history is downloaded automatically. However, you can download it yourself if you activate Symbols option.

Insert Charts Tools Window Help

Algo Trading New Order

Symbols

Specification Bars Ticks

EURUSD M1 2015.01.01 00:00 2020.10.06 16:55 Request

EURUSD,M1: 2054852 bars

Date	Open	High	Low	Close	Tick Volume	Volume	Spread
2020.10.06 14:25	1.17819	1.17826	1.17819	1.17824	11	0	1

Set the maximum allowable value of the candles available on the chart.

Magnet sensitivity: 10

Max bars in chart: 1000000

After installing the utility and downloading the history, you can start configuring the major and secondary parameters. First, you should understand that True Utility is a full-scale EA with the functions of a trading panel for manual / semi-automatic

or automatic trading based on the signals of the TrendLine PRO indicator:  
<https://www.mql5.com/ru/market/product/36087>

The indicator is not required, but its presence on the chart helps you set up the Utility correctly.

Magic is a unique number of orders traded by each EA. If you use multiple expert advisors on the same symbol, be sure to change the Magic

Lot Type serves to select the order calculation type. There are 3 lot types:

- Fixed size, meaning lot fixed size (e.g. 0.01)
- Floating (% of Balance), meaning floating lot size, set as % of the account balance (e.g. 5% for 1000\$ deposit, traded lot size is 0.05). The larger your deposit is, the larger is the traded lot.
- Risk, % of Balance (floating), the lot size is calculated for each deal. The further the Stop Loss is set in points, the smaller the size of the traded lot will be in proportion to the selected risk per trade.

TRADE UTILITY SETTINGS	
Magic	1111
Comment	TradeUtility_TL
Slippage	30
Lot Type:	% of Balance (floating)
Lot Size for TP1	Fixed size
Lot Size for TP2	% of Balance (floating)
Lot Size for TP3	Risk, % of Balance (need to set SL)
	5.0

**Percent DrawDown of Deposit for closing all orders** – you can use it as a stop level. When the specified % drawdown of the Deposit amount is reached, all the orders, which are open, will be closed.









**Take Profit type** - calculation of the TR level: Fixed level (Robot Type) or Indicator Settings (the level is set by the indicator). If you select a fixed level, specify its value in points in the next line.

Similarly, you can configure the Stop Loss level. NOTE: If you choose to calculate the order size as % Risk of Balance, you should specify the SL value.

Next, you can specify the Breakeven \_1 level for all orders TP1, TP2, TP3.

Breakeven\_2 level (offset to the entry level + spread) for orders TP2 and TP3 when the price reaches TP1

Breakeven\_3 level moves the breakeven to TP1 level for TP3 order, when the price reaches TP2

 Percent DD of Deposite for closing all orders	10.0
 TakeProfit type:	Robot type
 TakeProfit Value (for Robot type)	250
 StopLoss type:	Robot type
 StopLoss Value (for Expert Advisor type)	450
 Breakeven_1 for all TPs ( 0 - breakeven don't use)	100
 Breakeven_2 for TP2,TP3 on entry level (when reached T...	true
 Breakeven_3 for TP3 on TP1 level (when reached TP2)	true








The Trailing Stop parameter allows you to keep a target level (Stop Loss) for the price at a certain distance.

**Start trailing** is the distance which the price should pass to enable Trailing Stop.




**Dist tral by price** is the distance of SL level from the current price.

 ----- Trailing Setting -----";	
 Start tral (0 - Not Use)	250.0
 Dist tral by price	50.0












For all trades to open based on each indicator signal, set auto trading to AUTO mode, and the SuccessRate=0. The higher the limit for this parameter is, the less frequently transactions will be made.

 SuccessRate to open a deal (0 - don't use)	<b>0</b>
 SuccessRate_Type(Indicator type):	Average value
 MaxSpread of Symbol	500
 MaxDeviation Price of Symbol	500
 Trading Direction:	Any Deals
 Trade Mode:	<b>Auto</b>
 Unlimited time to make a Manual deals	false






Using the time filter allows you to limit the range of operation of the EA within a day. This parameter can only be used for intraday periods M1-H1.

 Use Open/Close Time Filter	true
 Type time filter	Trading Range
 Start Hour of Range	Trading Range
 Stop Hour of Range	Non-trading Range
	23

Set the parameters of the indicator and the EA in the same way so that the indicator signals match the signals of the EA. If you use the HTF filter, some trades will not be executed if the current signal does not match the signal of the older period that you selected.

 --- TrendLine PRO SETTINGS <u>(must be the same)</u> ---	
 Calculation type	method 2 (EMA)
 Amplitude	18
 Range Bars Number (RBN) for TP/SL level	35
 TP1 (Take Profit level)	0.4
 TP2 (Take Profit level)	1.7
 TP3 (Take Profit level)	3.0
 SL (Stop Loss level for all TPs)	1.5
 Close the deal at the opposite signal	true
 Use HTF-Filter	false
 Time Frame of HTF-Filter	4 Hours

Use notifications on your mobile or email to keep up to date with new signals of the EA.

 ----- NOTIFICATION SETTINGS -----	
 AlertON	true
 PushON	true
 EmailON	false
 ----- INTERFACE SETTINGS -----	

If you buy any INFINITY indicator or EA signed BUY 1 GET 1 FREE, you can get the second program for free. To do this, please leave your friendly feedback on the market and rate our work. See all the details here: <https://www.mql5.com/en/blogs/post/740436>.

We will also send you the HTF\_Histogram indicator (which displays HTF filter indication) and a link to our closed INFINITY group chat in Telegram.

Contact me: [profitcamp@mail.ru](mailto:profitcamp@mail.ru) or @EvgenyAks

I will be happy to answer your questions.

See our programs on the market page:

<https://www.mql5.com/en/users/neurofx/seller>