

Moving Average Cross Scanner Parameters

- A) As per the standard MA under MT4 >Indicators > Trend>Moving Averages.
1. Period
 2. Shift
 3. MA method:
 - a. Simple.
 - b. Exponential.
 - c. Smoothed.
 - d. Linear Weighted.
 4. Apply to:
 - a. Close.
 - b. Open.
 - c. High.
 - d. Low.
 - e. ETC.....
 5. Style
 - a. Colour.
 - b. Line.
 - c. Thickness.


I will need to be able to enter two different parameter MA's for my scanner.
My current moving average settings are:

- First moving average
 - a. Period: 5.
 - b. Shift: 0.
 - c. MA method: Simple.
 - d. Apply to: Close.
- Second moving average
 - e. Period: 5.
 - f. Shift: 2.
 - g. MA method: Simple.
 - h. Apply to: Close.

- B) To be able to enter up to 40 symbols for scanning.
- C) Must be able to enter the chart timeframe to be scanned for the ma cross. My preferred timeframe is the Daily.
- D) It will need a scanning period, example: On the Daily chart - today's candle (1 day) – today's candle & yesterday's candles (2 days) etc up to 5 days. (I normally scan the charts just before the end of the trading day – UK = 21.45)
- E) To be able to move the scanner around the chart.
 - a. example parameters:
 - i. Button colour. (default = Blue)
 - ii. Button Outline. (default = White)
 - iii. Font colour. (default = White)
 - iv. Font size. (default = 11)
 - v. Font face. (default = Arial)
 - vi. Corner. (default = 0)


- vii. Distance – x. (default = 25)
- viii. Distance – y. (default = 25)

- F) There must be a simple way to clear/reset the results of the scan.
 - a. Perhaps



or pressing the scan button resets the results before re-scanning.

- G) The scanner is not continually scanning – It only scans the symbols for a ma cross when the button is pressed.
- H) The scanner must be able to work from one chart.
- I) The results of the scan, to be viewed on the one chart – see example.



- J) All the charts will have the 2 x Moving Averages on.