

## INDICATOR NAME: MFR-VERTICAL LINES

-INDICATOR APPLIES VERTICAL LINE AT SPECIFIC DISTANCE FROM STARTING DATE.

-STARTING DATE IS SET MANUALLY BY DRAGGING ON CHART OR SET IN THE INPUTS.

-BY CLICKING RESET BUTTON THE STARTING WILL AUTOMATICLY RESET THE STARTING DATE 200 CANDLES BEHIND THE CURRENT CANDLE.

-BY CLICKING RESET ALL BUTTON, THE INDICATOR RESETS STARTING DATES OF ALL TIME FRAMES.

-INDICATOR WILL SAVE ANY CHANGES MADE IN ANY TIMEFRAME IN ITS LIBRARY FOLDER, WORKING AS MEMORY FILE.

-INDIACOR HAS 8 SETS OF VERTICAL LINES DISTANCE. SET CWILL BE SELECTED FROM ON SCREEN CONTROL PANEL.

-INDICATOR WILL HAVE 8 DIFFERENT SETS STARTING FROM SET 2 TO SET 9.

SET 2: 2-11-28-53-86-127-176-233-298-371-452-541-638

SET 3: 3-13-31-57-91-133-183-241-307-381-463-553-651

SET 4: 4-15-34-61-96-139-190-249-316-391-474-565-664

SET 5: 5-17-37-65-101-145-197-257-325-401-485-577-677

SET 6: 6-19-40-69-106-151-204-265-334-411-496-589-690

SET 7: 7-21-43-73-111-157-211-273-343-421-507-601-703

SET 8: 8-23-46-77-116-163-218-281-352-431-518-613-716

SET 9: 9-25-49-81-121-169-225-289-361-441-529-625-729

-CANDLE DISTANCE WILL BE WRITEN ON THE CHART. LOCATION OF THE CANDLE DISTANCE NUMBER CAN BE CHANGED IN THE INPUTS.

-COLOR AND LINE TYPE AND THICKNESS CAN BE CHANGED IN THE INPUT. ONE OPTION FOR STARTING DATE AND ONE OPTION FOR THE REST OF VERTICAL LINES.

-TIME FRAME CAN BE LOCKED FROM THE CONTROL PANEL. THIS OPTION WILL LOCK THE STARTING DATE AND ITS LINES SETTINGS AND SHOW THE SAME LINES ON ALL TIME FRAMES BY CLICKING ON THE **FIX** BUTTON ON THE CONTROL PANEL.



## INPUT SETTINGS:

Variable	Value
<b>StartDateSettings:</b>	<b>***StartDateSettings***</b>
StartDateDetect:	Auto/Manual (Auto represents manual on chart by hand and Manual represents by entering the date manually) <b>By default is Auto.</b>
StartDate:	_____ (If selected Manual)
StartingTime:	_____ (If selected Manual)
<b>ControlPanelSettings:</b>	<b>***ControlPanelSetting***</b>
ShowControl:	True/False. <b>By default is True</b>
ControlXpos:	10
ControlYpos:	100
ControlCorner:	Left Lower/Left Upper/Right Lower/Right Upper. <b>By default is Upper Right</b>
<b>LineColorSettings:</b>	<b>***LineColorSetting***</b>
StartDateColor	Color
StartDateStyle	2
StartDateWidth	0
SubLineColor	Color
SubLineStyle	2
SubLineWidth	0
<b>CandleDistanceNumbering:</b>	<b>*** CandleDistanceNumberingSetting***</b>
ShowDistance:	True/False. <b>By default is True</b>
CandleDistanceColor	Color
CandleDistanceFontSize	10
CandleDistanceLocation	Top Center/ Bottom Center
<b>NotificationSettings:</b>	<b>*** NotificationSettings***</b> (Notification is for when the price reaches at the opening of the un-triggered future line).
Email	True/False. <b>By default False</b>
Sound	True/False. <b>By default False</b>
Push	True/False. <b>By default True</b>
Message	True/False. <b>By default False</b>

For Assistance on how the indicator behaves am attaching an indicator named “AbuHamza Auto SQ9 V2” which will show how my indicator should work on the chart and how the library save option also works, am attaching an indicator that works the same way as I want but it’s for another purpose.