

KopirMT4 - Utility for MetaTrader 4, copy (synchronize duplicates) deal with any accounts.

KopirMT4- Utility for MT4, recognized by many managers and individual traders, please see reviews and commentary to the product. Unique algorithm exactly copy copies all transaction accounts Wizard on your client account. High speed of work. A large set of functionality. The high level of support.

Attention: the program works only locally on a PC or Windows VPS. This version does not work on virtual hosting VPS for MetaTrader 4.

Why choose our product?

- Xerox has a high work rate and does not depend on ticks. Copying speed is less than 0.5 sec.
- Transactions are copied with high accuracy mode "skal'pera" lets you copy only at the best price.
- Not losing ground when connection is broken or restart the Terminal.
- Do not ship the CPU and does not load on your PC or VPS.
- The number of terminals (client server) is not limited.
- Not using the DLL and does not transmit data to the Internet.
- May work with other advisers (experts) and scripts.
- Works correctly with the partial closure, without losing the spread on reopening.
- Can filter transaction to copy the parameters (see the instructions).
- Supports the "right" reverse transactions, taking into account the spread and the specified indentation.
- Can copy the transaction server when they are in black or in a given Bank.
- Works correctly with cross rates, metals, CFDS, stocks and futures, as well as on instruments with prefixes (automatic detection of prefixes).
- Recognize the differences in the name of metals and supports copying (XAUUSD, XAGUSD <-> GOLD <-> SILVER and others, you can configure any schema).
- Allows you to organize any copy schema from one account or multiple.
- We provide free information and support ready RM turnkey Setup.
- We are ready to listen to our customers and implement the required features to make our product even better.

Basic configuration copy

Configuring on master account (server)

1. install the purchased product on any chart in one instance. Leave the settings as default.
2. allow Live trading preferences and enable the Terminal button **Auto-trade**.

Configuring the client

1. install the purchased product on any chart in one instance.
2. mode select **Client** mode
3. Set the server account number (if multiple servers, you can specify a comma-separated list) **server accounts**
4. Set the multiplier lot **lot multiplier**, default 1

5. allow Live trading preferences and enable the Terminal button **Auto-trade**.

Settings:

- **Mode** -the role of this instance **Server** -mode of operation as the master account (the transferor). **Client** -mode of operation as a client. (host side)
- **Server accounts** -a list of numbers separated by commas, accounts from which the copy.
- **Delay Mode** -polling information on transactions **Timer** -survey on the built-in timer (fast reaction to changes in deals) **Tick** -ticks coming survey (slow responding to change transactions). This method is redundant and should be used when there are problems in the mode Timer.
- **History count (days)** -the number of history that treat analysis on closing transactions. It is recommended that you leave the default value.
- **Time manager use** -copy work on schedule
- **Monday, Tuesday, Wednesday, Thursday, Friday, Saturday, Sunday** - range the time in which it is permitted to Open transactions. The closure is not affected. Format: HH : MM - HH : MM Is allowed to indicate in the format HH - HH and you can also specify multiple ranges separated by commas. HH is hours, MM is the minute.
- **Filter magic list** -filter by magic ID transactions. (read more in the full instructions)
- **Filter symbols list** -filter by name server tools. **Attention:** This feature is not available in the free version. Free version works only on EURUSD.
- **Comment Filter list** -filter by comment or part thereof. (read more in the full instructions)
- **The minimum Filter** -Minimum lot server that allowed copy. 0-this feature is turned off
- **Maximum Filter** -Maximum lot server that allowed copy. 0-this feature is turned off
- **Copy mode** -copying mode. Feature allows you to copy, for example, only the specified direction Long or Short By default, copies Long and Short.
- **Timeout** time (in minutes) during which the copy is allowed to open the transaction. The default is no limit (0).
- **Reopen position** -function allows you to re-open a transaction at a price close to the source, if this transaction closed on the client.
- **Close price use** -mode activates a unique function for closing the transaction in profit on both the server. For example, if a server transaction closed in plus 1 item, then on the client, it too will shut down in 1 para. function is intended for copying skal'pirujushhih strategies.
- **Auto lot** -automatic calculation of the lot on the basis of the ratio of the balance of the client to the server with the given account currency and leverage. you can additionally adjust the lot using the lot multiplier.
- **Use balance or equity mode** - mode used with the Auto lot. Allows you to select a balance lead calculation or by equity.
- **Use currency accounts** -mode activates the recalculation of the lot, taking into account the currency conversion to function correctly, it is necessary to Review the market attended the right tool to get quotes. For example, if the expense of ruble, need the quotes tool USDRUB (USDRUR), if the expense of EUR or USD , EURUSD. If the account is in AUD, then need quotes AUDUSD.

- **Open minimal lot if the lot is 0** -Function allows you to open the transaction even if the estimated lot turns out is less than the minimum, in this case, the deal offers minimum fathomable. If this function is switched off and this scenario occurs, then the transaction is not copied.
- **Lot multiplier** lot multiplier. 1 = 100% of lots server. If you want to increase a lot in 2 times, then set the value of two. If you want to reduce in 2 times (1/2) specify a value of 0.5.
- **Fix alot** -If lot multiplier = 0, then uses a fixed lot.
- **Minimal lot for open** -If the current lot is less than the specified value, then open specified. 0-off
- **Maximal lot for open** -If the current lot is greater than the specified value, then open specified. 0-off.
- **Stop by equity** equity is the value at which the copying of new deals is prohibited. For example, if you have 500, and equity accounts became less than or equal to this value, the new deal will not be copied until equity will not be higher than the specified value.
- **Stop by margin level %** -the value of free margin in% where copies new transactions stopped. With increasing values above specified, it resumes.
- **Close all orders** -If the event specified in the settings came stopout balance or stopout margin level % then closes all open transactions.
- **Alert mail use , Alert push use** -send notifications about low equity or margin level at email or smartphone. Notification is sent at most 1 times in 10 minutes.
- **Copy limit orders** -copy limit orders or not by default the feature is disabled.
- **Copy of stop orders** -copy pending orders or not by default the feature is disabled.
- **Scaper mode** -scalper mode allows you to enter strictly on the exact costs or costs better by default is off. In this mode there may be omissions deals if the price has not returned to the entry point. Not suitable for copying strategies martingail.
- **Reverse mode** -the coup regime, such as transactions opened on the server BUY opens on the client SELL.
- **Points** -the profit or loss on points in which it is allowed to copy transaction. For example, if you specify -5, the transaction on the server will be equal to -5 items, it will be copied to the client at the current price.
- **Slippage is spread** -precision calculation mode of spread coefficient sign. If the function is disabled, then use the calculation in points.
- **Filter slippage** -the accuracy of the entry as a factor in the spread or paragraphs.
- **No close orders** -do not close the order on the client when they are closed on the server.
- **Count server all orders use** - read all the orders on the server during the activation orders count start
- **Count server orders copy start** -copy activation mode when there is a specified number of orders on the server
- **Count server copy orders stop** -stop ripping on a specified quantity of orders on the server
- **Client Count all orders use** - read all the orders on the client

- **Count client copy orders stop** -Stop mode on the client for the specified number of client orders
- **Auto comment** -automatic replacement of the commentary deals with information on the account number and ID of the transaction that is being copied.
- **User comment** -user comment for all transactions, if you specify a space (" "), then the comment is deleted transactions.
- **Pause for set takeprofit (min)** -delay (in minutes) prior to exhibiting the take profit from transactions
- **User can modify orders** -allows the trader or other advisers use to stop loss and take profit from client transactions
- **User takeprofit use** -install mode of their fixed take profit for all transactions
- **User taken at points** -profit in standard pukntah
- **User stoploss use** -install mode your stop loss for all transactions
- **User stop at points** - stop in standard paragraphs
- **No move stoploss and takeprofit** -feature automatically moves the stop and take on the size of the error log, if the transaction is opened by another price. its full description of settings in full instructions