

Description of parameters

(all parameters are entered as for usual four-digit accounts, for five-digit accounts they are recalculated automatically):

Parameters in the EA are given by default for brokers with GMT+1 (winter) or GMT+2 (summer)

--- GENERAL SETTING ---

Select Language; - select the language to display information on the chart and in the log.

Use Settings on the Chart; - Use the settings change in the chart Windows or in the standard EA settings window

New Cycle; - allows to stop and start the EA (duplicated by the button on the chart)

Max Spread; - Maximum spread at which the EA is allowed to open orders (duplicated by the button on the chart)

Start Time; - start Time of opening orders (duplicated by the setting on the chart)

End Time; - End Time open orders (duplicated setup on the chart)

Close All after (-1 not use); - Close all open orders after the hour specified in this parameter. If the value = -1, it is not used.

Use BE on Friday; – Use or not to close orders at no loss on Fridays. True – allow. False – deny.

Breakeven on Friday after; – Close all orders without loss on Friday, if they were not closed before the specified time (works with Use BE on Friday=True). After this time, the EA stops working and orders will not be opened until Monday. (duplicated the setup on the chart)

Disable trading on Wednesday; - Enable logic on Wednesday. If TRUE, orders will not be opened on Tuesday night. This is useful if you expect some very important events in which the market can behave very unpredictably (duplicated button on the chart)

Send Push if Drawdown (0.00 - not use); - Send a Push message to the smartphone if the drawdown level exceeds the specified value. If the value is 0.00 - disabled

Send trading operations; - Send (if TRUE) Push-messages about trading operations performed by the EA, such as opening orders, closing orders, profit, etc.

--- MONEY MANAGEMENT ---

Reserve in % - Percentage of reserve funds that will not be used for trading (duplicated by the setting on the chart)

Stop Out Level % (0.00 - not use) – When using the $\frac{1}{4}$ by $\frac{3}{4}$ money management strategy, this option will further limit losses if the value of this parameter is greater than 0.0. For example: if you set the value = 5.0, then if the free funds remaining from the reservation remain less than 5%, the EA will close all open transactions, regardless of whether they are profitable or at a loss (duplicated by the setting on the chart)

Use Autolot; - true - use autolot; false - do not use (duplicated by the button on the chart)

Autolot Size; - Number of tools to calculate the autolot (duplicated setup on the chart)

Initial Lot; - Initial lot size. (duplicated the setup on the chart)

When autolot = true, it is used to calculate the order volume by the formula: Initial Lot * Used funds / Autolot Size

Max Lot; - Maximum order volume.

Virtual Take Profit; - Virtual take profit level at which the EA will close orders in profit (duplicated by the setting on the chart)

Virtual Stop Loss; - Virtual stop loss at which the EA will close orders with a loss (duplicated by the setting on the chart)

Calculate dynamic stop loss automatically; - Calculate virtual stop loss dynamically depending on market volatility (duplicated by the button on the chart)

Use Lot Multiplier; - Use (if TRUE) the multiplier of the next lot (duplicated by the button on the chart)

Lot Multiplier; - Multiplier of the next lot. Up to three orders will multiply the previous volume by the value specified in this parameter. Starting from the fourth order, the volume increase will be slightly different algorithm, so as not to increase a large volume (duplicated setting on the chart)

Max Open Orders (one direction); - Maximum allowed number of orders in one direction. When using the next lot multiplier, a value greater than 6 is not recommended. (duplicated the setup on the chart)

Use Max Open Orders Per Day; - Use the maximum number of orders per day. If = TRUE, the EA will open orders on the day, no more than specified in the Max Open Orders parameter

Take Profit for broker; - Take profit for broker

Stop Loss for the broker; - Stop loss for the broker

Use Average TP SL; - Allows you to disable (if FALSE) or enable (if TRUE) averaging of take profit and stop loss levels that are set for the broker. If the parameter is disabled (FALSE), if the take profit level for the broker is set by 1-2 points more than the virtual take profit (but not more), then in some cases you can get additional profit, because some orders can be closed by the take profit level for the broker, and not by the virtual take profit. When the parameter is enabled (TRUE) , the take profit level for the broker does not matter, because orders will be closed at the virtual level, and the real levels will be averaged.

Close Grid Parts; - If TRUE, the EA will close the grid in parts, in pairs, the largest in volume with the smallest, as well as in drawdowns, it will build a grid and also close it in pairs to quickly get out of the drawdown and maintain the equity level.

Grid step, point; - the Number of points to draw a grid to exit the drawdown.

Minimal profit for close grid, point; - Minimum profit in points for closing pair orders (the largest in volume and the smallest).

--- CONFIGURE INDICATORS ---

Signal Indicator Period; - Period for the first signal indicator

Signal Indicator From; - the Lower level of the first signal indicator

Signal Indicator To; - the Upper level of the first signal indicator

Confirm Indicator Period; - Period for the confirming indicator

Confirm Indicator From; - the Lower level of the confirming indicator

Confirm Indicator To; - the Upper level is a confirming indicator

Confirm Indicator TF; - Time frame for confirming indicator

Signal Indicator2 Period; - Period for the second signal indicator

Signal Indicator2 Max; - Maximum value for the second signal indicator

Signal Indicator2 Min; - Minimum value for the second signal indicator

"--- NEWS SETTING ---"

Disable trading during news release; - Disable trading during news release

Enable Low News; - Use (if TRUE) weak news

Pause before Low News, minutes; - Pause before the release of weak news

Pause after Low News, minutes; - Pause after weak news

Enable middle News; - Use (if TRUE) average news

Pause before Midle News, minutes; - Pause before entering secondary news

Pause after Midle News, minutes; - Break after the release of the medium of news

Enable High News; - Use (if TRUE) important news

Pause before High News, minutes; - Pause before important news

Pause after High News, minutes; - Pause after important news

Enable NFPNews; - to Use (if TRUE) NFP news

Pause before NFPNews News, minutes; - Pause before NFP news release

Pause after NFPNews News, minutes; - Pause after NFP news

DrawNewsLines; - Draw (if TRUE) news lines on the chart

Display the news text next to the line; - Display (if TRUE) the names of the news on the chart

Broker Time Zone, GMT (for news); - Deviation from GMT for news output (duplicated by the setting on the chart). Do not forget about this parameter when setting the trading time, otherwise the news will not be received in time and it can significantly affect the trade!

--- SETTINGS UNIT INFORMATION ---

Use Order Comment; - If True – orders will be assigned a comment for easy tracking of positions opened by the robot in the terminal. If False – all positions will be without comments.

Show Info Table; - true - show; false - do not show.

Font Size; - font Size for information block and buttons.

Magic Number - - magic number to distinguish your orders from other

Show Chart Grid; - enables and disables the grid display on the chart