

[__ GENERAL PARAMETERS __]	
Play Sound on Profit Closing	Plays a sound if profit orders have been closed
Play Sound while Profit Trailing	Plays a tick sound during profit trailing activity
Display Panel	If enabled, displays Onscreen Panel
Magic Number	Unique Magic Number to differentiate from other Experts orders on the current account. Always make sure that other Experts are set to different Magic Numbers!
Position Comment	Individual comment added to opened orders
Panel Background Color	Selection of Onscreen Panel background color or default image
[__ CAPITAL/RISK PARAMETERS __]	
Acc. Free Amount Mode	Selectable between Balance, Equity and Margin. (Margin or Equity are the less risky modes)
Acc. Max. Free Amount(%) to utilize (0=disabled)	Limits the total account amount that can be used by the Expert to that preset percentage
Acc. Risk(\$)/0.01 Lot for Initial Position (0=disabled)	Presets of the amount that is used per "Lotsize Fix". Example: If set to \$1000, 0.01 Lot becomes used for every \$1000 of the account balance. In case of a \$5000 account, the lotsize for the initial order would start with 0.05 lots. If the profit reaches \$1000, then the next initial orders will start with 0.06 lots.
[__ VOLUME PARAMETERS __]	
Lotsize Fix. for Intitial Position (if Risk(\$)/0.01 Lot = 0)	Minimum start lot size to open an initial order.
Lotsize Max. for Intitial Position (if Risk(\$)/0.01 Lot > 0)	Maximum lot size allowed for opening an order.
[__ TRADING PARAMETERS __]	
Trade Positions Long	Maximum of opened Buy orders
Trade Positions Short	Maximum of opened Sell orders
Max. Positions to be open (incl. Grid)	Maximum of opened Buy/Sell orders
Max. Slippage	Maximum Slippage allowed for opening an order
Max. Spread	Maximum Spread allowed for opening an order
[__ REDUCTION PARAMETERS __]	
Max. Reduction Positions Long (0=disabled)	Maximum Buy orders allowed for starting a reduction action
Max. Reduction Positions Short (0=disabled)	Maximum Sell orders allowed for starting a reduction action
Min. Reduction Distance (0 = Grid disabled)	Minimum distance between the last Grid order and the current price. The distance might increase if the price moves further in the opening direction by virtual trailing.
Reduction Scaling Mode	Raising factor of grid orders. Examples: Arithmetic: 1, 2, 3, 4, 5, 6, 7,... <= max. Lot size Geometric: 1, 2, 4, 6, 8, 10, 12,... <= max. Lot size 'e' to the Power of 2: 1, 1, 2, 4, 8, 16, 32,... <= max. Lot
Reduction Scaling Base	Defines the base of Reduction Scaling: - Minimum trade volume x open volume - Orders count
[__ CLOSING PARAMETERS __]	
StopLoss per Position (0=disabled)	Stop loss in Points for each single order
Drawdown Reduction Use	Enable/Disable Drawdown Reduction. Also switchable at the Onscreen Panel
Drawdown Reduction open Orders Start (0=disabled))	Minimum of open orders before Drawdown Reduction becomes activated. Only valid if Drawdown Reduction Use is activated.
Drawdown Compensation open Orders Start (0=disabled))	Minimum of open orders before Drawdown Compensation becomes activated. If activated, it searches for orders in profit and compares it with orders in loss

	territory. If an order's loss value multiplied by (-1) is less than the value of the profitable order, both orders become closed so that the Account's Margin Level become reduced. This option is especially useful on low Leverage accounts, e.g. 1:30.
TakeProfit Grid Trail Activation	Minimum Profit to start the virtual take profit trailing
Min. Profit(%) saved @Trail Activation	Minimum percentage saved of the profit when the "TakeProfit Grid Trail Activation" is starting.
[__ TRADING TIME PARAMETERS __]	
Monday Start Hour (0 = disabled)	Self-explanatory
Weekday Start Hour (0 = disabled)	Self-explanatory
Weekday Stop Hour (0 = disabled)	Self-explanatory
Friday Stop Hour (0 = disabled)	Self-explanatory
December Stop Day (0 = disabled)	If used, trading stops at the given day of December and ends at 31. December.
January Start Day (0 = disabled)	If used, trading stops at the 1st of January and starts again after the given day.
[__ NEWSFILTER SETTINGS __]	
Use Pause on Events	Activate/Deactivate to pause on preset events.
Draw Events Timelines	Shows times of predefined events.
Use Auto GMT Update	Activate/Deactivate automatic GMT detection.
GMT Diff. (used if Auto GMT = Disabled)	Manual set GMT difference.
Show News from Symbols	List of Currencies from which news should become selected for displaying on the Onscreen Panel News Page.
[__ 1=Low,1=Mid,1=High,1=Very High __] (0=Disabled)	Explain of the meaning of the "Selected Event Levels".
Selected Event Levels	Examples: All Levels: 1,1,1,1 Only medium and high important levels: 0,1,1,0
[__ Selected News Level (set 0,0 if not used) __]	
Pause Low Events	Example: 15,15 stops Trading 15 minutes before the news and start it again after 15 minutes after the news event started.
Pause Middle Events	See previous example.
Pause High Events	See previous example.
Pause Very High Impact Events	See previous example.
Show Past Events in Hours	Allows to display a range of past News .
[__ MISCELLANEOUS __]	
Display Panel in visual Tester Mode	Default disables as if enabled it slows down the backtest.